

Blueprint 6.2

User Guide

Contents

Introduction	12
About running Blueprint in unsafe mode	12
What is unsafe mode?	12
What Blueprint features do not function in unsafe mode?	12
Running Blueprint in unsafe mode	12
About elevated trust in-browser	13
What is elevated trust in-browser (also known as 'elevated trust')?	13
What Blueprint features require 'elevated trust'?	13
Is 'elevated trust' secure?	14
How do I know if I have elevated trust in-browser enabled?	14
Configuring elevated trust in-browser	14
How to configure elevated in-trust browser	15
How to configure elevated in-trust browser (Windows XP users only)	17
Textual requirements	17
Textual Requirement Artifact Properties	18
Adding a textual requirement	18
Creating and editing textual requirement content	18
Using the textual requirements editor	19
Rich text formatting	19
Deleting a textual requirement	20
About rich text formatting	20
Rich Text Formatting in the Artifact List	20
Use cases	22
Use Case Artifact Properties	22
About the use case editor layout	23
Use Cases Group on the Ribbon View Tab	23
Use Cases Ribbon Tab	24
Adding a use case	25
Building a use case	25
Key Terms and Concepts	25
Typical use case creation	26
Use Case Example	26
Adding use case steps	26
Deleting use case steps	27
Merging use case steps	27

Rearranging the order of use case steps and flows	28
Adding an actor to a use case step	28
Including a use case in a step	29
Adding an internal alternate flow	30
Flow Conditions	30
Adding an external alternate flow	31
Flow Conditions	32
Changing an external use case	32
Setting start and return steps	32
Setting UI mockups on use case steps	33
Removing a UI mockup from a use case step	33
Deleting a use case	34
About use case simulation	34
Overview	34
Simulating a use case	35
Navigating your Use Case Simulation	35
Overview	35
Navigation markers	36
Changing the scope of the Use Case Simulation	37
Using the Navigation Controls	37
Starting the simulation at another step	38
Actor-system interaction and alternate flows	38
Using keyboard shortcuts during use case simulation	38
Keyboard shortcuts for font editing operations	39
Keyboard shortcuts for simulation navigation	39
Keyboard shortcut to refresh	40
Keyboard shortcuts to access helpful information	40
Viewing a list of shortcuts	40
UI mockups	41
UI Mockup Properties	41
Adding a UI mockup	41
Deleting a UI mockup	42
Previewing a UI mockup	42
Interactive and non-interactive widgets	42
About screen captures	43
Applicability	44
Adding a screen capture to an artifact	44

Glossary artifacts	44
Glossary Artifact Properties	45
Adding a glossary	45
Deleting a glossary	45
Adding a new term directly to the glossary	46
Adding a new glossary term from another artifact	46
Linking to an existing glossary term from other artifacts	46
Editing a glossary term	47
Deleting a glossary term	47
About Storyboards	47
Storyboard Artifact Properties	47
Adding a storyboard	48
Deleting a storyboard	48
Actors	48
Actor Artifact Properties	48
Adding an actor artifact	49
Setting and removing actor inheritance	49
Setting and removing an actor image	50
Deleting an actor artifact	51
Business process diagrams	51
Business Process Diagram Artifact Properties	51
Adding a business process diagram	51
Deleting a business process diagram	52
About Generic Diagrams	52
Generic Diagram Artifact Properties	52
Adding a generic diagram	53
Deleting a generic diagram	53
About Domain Diagrams	53
Domain Diagram Artifact Properties	53
Adding a domain diagram	54
Deleting a domain diagram	54
About use case diagrams	54
Use Case Diagram Artifact Properties	55
Adding a use case diagram	55
Deleting a use case diagram	55
Document artifacts	56
Document Artifact Properties	56

Adding a document artifact	56
Uploading a file to a document artifact	57
Deleting a document artifact	58
User stories	58
User Story Artifact Properties	58
Adding a user story	58
Deleting a user story	59
Epics	59
Epic Artifact Properties	59
Adding an epic	59
Deleting an epic	60
Themes	60
Theme Artifact Properties	60
Adding a theme	60
Deleting a theme	61
Features	61
Feature Artifact Properties	61
Adding a feature	62
Deleting a feature	62
Scenarios	62
Scenario Artifact Properties	63
Adding a scenario	63
Deleting a scenario	63
About rich text tables	63
Copying and pasting rich text tables to and from other applications	64
Copying tables from Blueprint and pasting in Microsoft Office documents	64
Copying tables from Microsoft Office documents and pasting in Blueprint	64
Adjusting the height of a cell	64
Adjusting the width of a table	65
Changing the border styling (color and weight) of a table or cell	66
Deleting cells in a table	66
Inserting a new row or column	67
Merging and splitting cells	68
Merging cells	68
Splitting cells to undo a merge	68
Reusing requirements artifacts	68
Overview	68

Reconciling reused artifacts	69
About spell check	69
Recommended spellings	69
Ignore all	70
Adding a term to the Dictionary	70
The difference between Ignore All and Add to Dictionary	71
The difference between spell check and the glossary	71
Adding a term to the Dictionary	72
Disabling the spell checker	72
Enabling the spell checker	72
About locks	73
Overview	73
Stealing a lock	73
View management and saved views	74
Saved Views	75
Saved View Types	76
Selecting a view	76
Adding a new view	77
Duplicating a view	78
Modifying a view	78
Deleting a view	79
Expanding or collapsing all artifacts in the artifact list	79
About Global Search	80
Using an operator in your search	81
Search results	82
Searching for artifacts	83
About the utility panel	84
Overview	84
Resizing and expanding/collapsing the utility panel	85
Understanding the utility panel tabs	85
About artifact properties	86
Understanding the properties tab in the utility panel	87
Viewing and changing artifact and sub-artifact properties	87
Performing a bulk update	88
Artifact outline	89
Applicability	90
Displaying the outline view of an artifact	90

Expanding or collapsing all artifacts in the artifact list	91
Artifact searching and browsing	92
Browsing artifacts	92
Opening artifacts from the utility panel browse tab	93
File attachments and document references	93
Determining whether or not an artifact contains file attachments or document references	94
Adding a file attachment to an artifact	94
Adding a document reference to an artifact	95
Opening a file attachment or document reference	95
Deleting a file attachment or document reference	96
About rich text formatting	96
Rich Text Formatting in the Artifact List	97
Keyboard shortcuts	98
Keyboard shortcuts for basic operations	98
Viewing a list of shortcuts	102
Keyboard Navigation	102
Choice Drop-Down Keyboard Navigation	103
Multi-Select Keyboard Navigation	103
Select Users Dialog Keyboard Navigation	104
Moving artifacts from one project to another project	104
Data preservation differences between cross-project move and cross-project copy	104
Undoing an artifact move	105
Moving an artifact from one project to another project	105
About copying and pasting	106
Copying and pasting text	106
Copying and pasting text examples	106
Pasting shapes	107
Pasting Visio shapes	107
Copying artifacts	107
Pasting text in a diagram	107
About pasting images	108
Pasting an image into Blueprint	108
Importing and Exporting	109
About Excel update	109
Formatting requirements	109
Specifying custom property values	110
About generating an Excel update template	110

About exporting and importing rich text formatting using Excel update	111
Updating artifacts using Excel	112
Generating an Excel update template	114
Importing new requirements from Microsoft Excel	114
Importing glossary terms from Microsoft Excel	117
Exporting an artifact list view to Excel	117
Collapsed and expanded artifacts	118
Preserved column details	118
About ALM integration	119
What data is exported to the ALM system?	119
Example	119
Exporting artifacts for the first time	119
Exporting artifact changes and deletions	120
Exporting artifacts to an ALM Target	121
Overview	121
Setting up the export	121
Performing the export	122
About Visio integration	123
About importing Visio diagrams	123
About External Shapes	124
About exporting Visio diagrams	124
Importing a Visio diagram	124
Requirements	125
Exporting a diagram to Visio	126
Requirements	126
About artifact printing	126
Overview	126
Output file	127
Modifying the default print template at the project level	129
Printing a historical version of your artifact	130
Printing an artifact to a PDF document	130
Printing an artifact to a Word document	131
About job management	131
Job types	132
Job operations	133
Job statuses	133
Canceling a job	134

Checking the status of a job	134
About notifications	135
About saving artifacts as images	135
Applicability	136
Supported image formats	136
Saving an artifact as an image	136
About test generation	137
Example	137
Generating a test plan	138
Social collaboration	140
About the activity center	140
Removing items from your activity center	141
About discussions and commenting	142
Determining whether or not an artifact contains open discussions	142
Viewing comments in the utility panel	143
Adding a new comment	143
Mentioning someone in a comment	144
Overview	144
Replying to an existing comment	145
Changing the status of a discussion	145
About artifact sharing	146
Sharing artifacts from the utility panel browse tab	146
Artifact versioning and history	147
Understanding the utility panel history tab	147
Sorting and filtering historical versions	148
Sorting versions	148
Filtering versions	148
Filtering by Version Number	148
Filtering by Author	149
Filtering by Date	149
Viewing a historical version of an artifact	150
Viewing the changes between two historical versions	150
Understanding the changes	150
Viewing the changes between two versions of an artifact using Side by Side	151
About Version Compare	152
Overview	152
Version Compare report	153

Different ways of accessing Version Compare	154
Comparing versions of an artifact	154
Exporting a Version Compare report to Excel	155
About Baselines	155
Finding your baseline artifacts	156
Typical Baseline Usage	156
Baseline Artifact Properties	156
Creating a new baseline	157
Configuring and sealing a baseline	157
Viewing baseline contents	158
Deleting a baseline	159
Adding an artifact to a baseline	159
Adding an artifact to a baseline	160
Traceability and relationships	161
Trace Types	161
Viewing and filtering relationships	162
Adding traces from the relationships tab in the utility panel	162
Adding traces from the utility panel browse tab	163
Adding an inline trace	164
Changing the direction of a trace	165
Adding and removing the trace suspect flag	165
Deleting a trace	166
About the traceability explorer	167
Exporting a traceability matrix to Microsoft Excel	168
Exporting a traceability matrix to Excel	168
Exporting a traceability matrix to Microsoft Word	168
Exporting a traceability matrix to Word	169
Viewing trace relationships in a matrix	169
Collections	170
Baselines and reviews	170
Finding your baseline and review artifacts	171
Reviewer and Approver Roles in Formal and Informal Reviews	171
Baseline and Review Examples	171
About Reviews	172
Finding your review artifacts	172
Key Concepts	173
Reviewer and Approver Roles in Formal and Informal Reviews	173

Review Status	173
Modifying an Active Review	173
Typical Usage of Reviews	173
Review Artifact Properties	174
Adding a review	174
Configuring a review	175
Modifying an Active Review	177
Adding artifacts to an existing review	177
Viewing review status information	178
Overview Layout	179
Details Layout	180
Contents Table	180
Reviewer Participants Table	180
Closing a review	181
Creating a follow up review	182
Deleting a review	182
About the utility panel reviews tab	183
Understanding the review summary table	183
Understanding the review details	184
About the Reviewers Experience	184
A Typical Review Process	184
About the reviewers experience layout	184
Features and menu functions	185
Review details	186
Adding comments to an artifact in a review	187
Changing the approval status of an artifact	188
Changing your review status	189
About electronic signatures	189
Electronic signatures and approvers	189
Requesting electronic signatures for a formal review	191
Generating an office document	192

Introduction

Blueprint is a powerful requirements solution that allows users to collaboratively author, validate, and manage requirements. This guide is intended for end users of the Blueprint product. New users will want to begin with the Blueprint Getting Started Guide. Blueprint instance administrators and project administrators can refer to the Instance Administration Guide and Project Administration Guide to learn how to administer the system.

About running Blueprint in unsafe mode

What is unsafe mode?

Blueprint provides a rich, interactive application experience that is secure and requires access to a greater set of resources in order to operate effectively. When running Safari for Mac, Apple recognizes there are many applications that could need access to a greater set of resources and to work with local applications. Therefore, they have provided a sanctioned way (*unsafe mode*) to enable a way to run Silverlight in a more privileged mode while still running within the web browser.

What Blueprint features do not function in unsafe mode?

Although unsafe mode enables many Blueprint features, Safari restricts the following Blueprint functionality:

- **Screen capture:** This is the built-in capability that allows the user to capture images of their windows and drop them directly into their graphical artifacts in one click. Silverlight by default does not allow the user to access other windows. Screen capture is still possible via importing an image file saved to disk.
- **Pasting images:** Silverlight by default revokes access to the clipboard for images, therefore any images that may be on the user's clipboard cannot be pasted into Blueprint. For example, if you had an image in your Microsoft Word document you wanted to paste into Blueprint, you would not be able to paste the image.
- **Rich text table integration with other applications:** Because Silverlight by default revokes access to the clipboard, the user cannot paste tables that are on their clipboard. For example, if you have a table in your Microsoft Excel document you wanted to paste into Blueprint, you would not be able to.
- **Visio import/export:** Our integration with Visio requires direct access to the Visio application on the client computer. Safari and Silverlight by default allow no such direct application access based on the default security model. Therefore, access to Visio is not supported.

Running Blueprint in unsafe mode

Safari does not support running Blueprint in safe mode because access to Silverlight is needed to run Blueprint. You must run Blueprint in unsafe mode in order to use Silverlight and, thus, Blueprint. For more information about running Blueprint in unsafe mode, see [About running Blueprint in unsafe mode](#).

To run Blueprint in unsafe mode, complete the following:

1. Open Blueprint in Safari.
2. Select *Safari* on the menu bar and then click **Preferences**.

The *Preferences* dialog appears.

3. Select the *Security* tab.
4. Click the **Manage Website Settings** button.
A list of web sites appears.
5. Select your Blueprint web site.
A pop-up menu appears.
6. Select **Run in Unsafe Mode**.
An alert message appears.
7. Click **Trust**.
8. Click **Done**.
9. Close the *Preferences* dialog.
10. To see the change, refresh your browser.

You have successfully configured Safari to run Blueprint in unsafe mode.

About elevated trust in-browser

What is elevated trust in-browser (also known as 'elevated trust')?

To answer this question, you must first understand the kind of environment Blueprint runs in. Blueprint runs in your web browser under Silverlight. This provides a rich, interactive application experience while at the same time being secure without any major client footprint. Blueprint has virtually no access to hardware and operating system level resources unless Silverlight explicitly allows it. In This gives people peace of mind that any Silverlight application can only operate in their own 'sandbox' without affecting anything outside of the application.

However, Microsoft did recognize that there are many applications that could need access to a greater set of resources and a need to work with local applications. Therefore, they provided a safe and sanctioned way to enable a way to run Silverlight in a more privileged mode while still running within the web browser. The full name is 'Elevated Trust in browser' but we will call it 'Elevated trust' for the rest of this text.

What Blueprint features require 'elevated trust'?

Blueprint specifically leverages this mode for a few (optional) operations:

- **Screen capture:** This is the built-in capability that allows the user to capture images of their windows and drop them directly into their graphical artifacts in one click. Silverlight by default would not allow the user to access other windows unless their privileges are elevated. Screen capture is still possible via importing an image file saved to disk.
- **Pasting images:** Silverlight by default revokes access to the clipboard for images, therefore any images that may be on the user's clipboard could not be pasted into Blueprint without additional privileges. For example, if you had an image in your Microsoft Word document you wanted to paste into Blueprint, you would not be able to without elevated trust.
- **Rich text table integration with other applications:** Because Silverlight by default revokes access to the clipboard, the user needs the additional privileges to paste tables that are on the user's clipboard. For example, if you have a table in your Microsoft Excel document you wanted to paste into Blueprint, you would not be able to without elevated trust.

- Visio import/export: Our integration with Visio requires direct access to the Visio application on the client computer. Silverlight by default allows no such direct application access based on the default security model. Therefore, privileges would need to be elevated in order to allow this access.

Is 'elevated trust' secure?

Does 'Elevated trust' open a security hole?

There is a very strict, and detailed admin-involved process required to enable elevated trust. This can be only be done by a trusted administrator on the local client machine without any way to subvert this.


Once 'Elevated trust' is configured, has Silverlight security for the entire machine been dropped?


Not at all. Once this is done, the client machine knows that it needs to allow an application with Blueprint's certificate to run in an elevated mode. This gives Blueprint additional permissions that any other Silverlight application on the machine would NOT have.

Every Silverlight application would have to follow a similar process in order to enable them specifically. On top of this, nobody can spoof our private Blueprint certificate and create a rogue elevated application.

Even with elevated trust, this is something we leverage sparingly. We do not go outside of the standard Silverlight boundaries unless we absolutely need to in order to accomplish a specific task, such as Visio in/out or screen capture. If you feel you (or a particular user) will never use these features, you do not need to run in elevated mode at all. All other parts of Blueprint will function without issue.

How do I know if I have elevated trust in-browser enabled?

You can check whether elevated trust in-browser is enabled by opening the *Profile Options* screen that is located on the **application** menu .



Configuring elevated trust in-browser

Tip: This whole process has been purposely designed to be centrally managed and deployable via Group Policy if your organization works in that manner. Refer to the *Blueprint Installation Guide* for more information.

Note: If you are running Windows XP, you have two configuration options: you can follow the [instructions for configuration via the Microsoft Management Console](#) --or-- you can install the Microsoft Windows Server 2003 Administration Pack in order to obtain the **certutil.exe** program that is necessary to configure elevated trust in-browser.

Learn more about [how to determine if elevated trust in-browser is enabled](#).

Installation Overview

At a high level, enabling elevated trust in-browser is a two step process:

1. Inform Silverlight that a specific application will require elevation. This is achieved by adding the key (`AllowElevatedTrustAppsInBrowser` with a value of `DWORD:1`) to the registry. This key tells Silverlight that there is an application that will require elevated trust mode.


Note: No elevation has occurred as a result of this step. This step simply tells Silverlight to allow for a specific application to request elevation.

2. Inform Silverlight that Blueprint (and *only* Blueprint) needs to run in an elevated mode. This is achieved by installing a certificate that uniquely identifies the Blueprint application.

How to configure elevated in-trust browser

To configure Blueprint to run with elevated trust in-browser, perform the following steps on each client:

1. Download the [elevated trust in-browser configuration files](#).
2. Unzip the package and note the directory where the files are located.
3. Run **cmd.exe** as Administrator.
 1. Click the Windows **Start** menu and type **cmd.exe** into the search bar.
 2. Right-click the **cmd.exe** program that appears under the Programs heading and then select **Run as administrator**:



3. When the confirmation dialog appears, click **Yes**.

The **cmd.exe** application launches with Administrator privileges:

4. Use the **cd** command to navigate to the folder where you unzipped the files.

For example:

```
cd c:\temp\elevated_trust
```

5. Enter the following commands to allow elevated trust to run on your local machine:

- For 64-bit operating systems:

```
regedit.exe /s AllowElevatedTrustAppsInBrowser64.reg
```


- For 32-bit operating systems:

```
regedit.exe /s AllowElevatedTrustAppsInBrowser.reg
```

6. Run the following **certutil** command to apply the Blueprint public certificate:

```
certutil.exe -f -addstore "TrustedPublisher"  
publicBlueprintCertificate2017.cer
```

Here is an example of the commands run on a 64-bit operating system:



```
Administrator Command Prompt
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Windows\system32>cd c:\temp\elevated_trust
c:\temp\elevated_trust>regedit.exe /s AllowElevatedTrustAppsInBrowser64.reg
c:\temp\elevated_trust>certutil -f -addstore "TrustedPublisher" publicBlueprintCertificate.cer
TrustedPublisher
Certificate "CN=Blueprint Software Systems, OU=Digital ID Class 3 - Microsoft Software Validation v2, O=Blueprint Software Systems, L=Toronto, S=Ontario, C=CA" added to store.
CertUtil: -addstore command completed successfully.
c:\temp\elevated_trust>
```

7. Restart your web browser for the changes to take effect.

How to configure elevated in-trust browser (Windows XP users only)

1. Click the **Start** button and then type “mmc.exe” in the search field.
The search results appear.
2. Click **mmc.exe** in the Programs list results.
A *user account control* dialog box appears.
3. Click **Yes**.
The *Microsoft Management Console* appears.
4. From the **File** menu, click **Add/Remove Snap-in**.
5. Select *Certificates* and then click the **Add** button.
The *Certificates snap-in* dialog box appears.
6. Select **Computer account** and then click **Next**.
7. Select **Local computer**.
8. Expand *Trusted Publishers*.
9. Right click *Certificates > All tasks > Import*.
10. Locate the file **publicBlueprintCertificate2017.cer** and place the certificate in *Trusted Publishers*.

Once the certificate is imported, you can see the Blueprint Software Systems certificate in *Trusted Publishers*.

Textual requirements

A *textual requirement* artifact is a documented property or capability that a product must possess to provide value to a stakeholder. In this case, the requirement is documented in a textual (as opposed to visual) form.

Textual requirements are beneficial if you need to capture requirements rapidly. Once captured, textual requirements are often used as the basis for visualizing requirements using other types of artifacts such as use cases and UI mockups.

Textual requirements, like all other artifacts, can be organized in a hierarchy. You can enhance your textual requirements by taking advantage of rich text formatting. You can also attach files to your textual requirements, and trace your textual requirements to other artifacts.

To support your existing business processes and standards, project administrators can customize the set of requirement types, and create other custom properties as needed.

Textual Requirement Artifact Properties

By default, a textual requirement artifact contains the following system properties:

- **Name:** Indicates the name of the **textual requirement**.
- **Id:** Provides a unique identifier for the **textual requirement**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Description:** Provides the description of the textual requirement.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a textual requirement

To add a textual requirement artifact:





1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **textual requirement** icon .

Creating and editing textual requirement content

You can edit a textual requirement from the artifact list, or by opening the artifact. You may be interested in learning more about [keyboard navigation shortcuts](#) to improve your efficiency.

Tip: If you are editing many requirements at once, it may be more efficient to edit the content directly from the artifact list, which provides you with an *edit in place* experience.

To do this, use the **Column Options** button on the *View* tab and select only the fields you need to see in the artifact list. Next, place a checkmark in the **Wrap Text** option. You can now view the textual requirements in a table style. Example

Amazon.com > Requirements > Stores > General > Gift Cards >			
PF7757: Business			
	Name	ID	Description
	Disputes	BR7747	Any dispute relating in any way to Gift Certificates in which the aggregate total claim for relief sought on behalf of one or more parties exceeds CDN \$7,500 shall be adjudicated in any state or federal court in King County, Washington, and you consent to exclusive jurisdiction and venue in such courts.
	Redemption	BR7761	Gift Certificates must be redeemed through the Amazon.ca Web site, http://www.amazon.ca , toward the purchase of eligible products. Purchases are deducted from the Gift Certificate balance. Any unused balance will be placed in the recipient's Gift Certificate account when redeemed. If an order exceeds the amount of the Gift Certificate, the balance must be paid with a credit card or other available payment method. Amazon.ca may provide Gift Certificate purchasers with information about the redemption status of Gift Certificates. To redeem or view Gift Certificate balances, visit " Your Account " on Amazon.ca.
* 	Limitations	BR7762	There are limitations on the use of gift cards
	Risk of Loss	BR7739	The risk of loss and title for Gift Certificates pass to the purchaser upon our electronic transmission to the recipient. We are not responsible if a Gift Certificate is lost, stolen, destroyed or used without your permission.

Simply click the *Description* of any textual requirement to edit the text. You can also take advantage of rich text formatting.

To create or edit textual requirement content:

1. Open a textual requirement artifact.

Click the artifact ID link of the **textual requirement** artifact you want to open.

2. Provide a name for the textual requirement.

Type a name into the `Name` field.

Tip: We recommend that you choose a name that is descriptive, but relatively short in length.

3. Set the textual requirement type.

Click the `Type` drop-down menu and select a type from the drop-down list. There is only one type by default (**Textual Requirement**), but your project may have custom types configured (example: **Business Requirement** or **Functional Requirement**).

4. Set any additional custom properties.

Custom properties vary from project to project and are configured by your Blueprint project administrator.

5. Provide a description for the textual requirement.

See [Using the textual requirements editor](#) for more information about formatting and enhancing your textual requirements in Blueprint.


Note: You must publish the artifact before your changes are viewable by other users.

USING THE TEXTUAL REQUIREMENTS EDITOR

To enhance your requirements, you may want to use the utility panel to [add an attachment](#) or [create a trace](#) to other artifacts. You can also take advantage of many rich text formatting features, such as creating lists or adding a hyperlink to your textual requirements.

Rich text formatting

Blueprint provides you with the ability to create textual content using rich text formatting. In other words, you can perform many of the operations that you can perform using a word processing application. The rich text formatting features are available on the ribbon *Home* tab:



Here's a list of the rich text formatting features offered by Blueprint:

- Change font type, color, and size
- Make the font bold, italic, underline, subscript, superscript, strikethrough
- Apply highlighting to font
- Add a hyperlink
- Create a bulleted or numbered list
- Change the paragraph justification

Deleting a textual requirement

To delete a textual requirement:

1. Open the **textual requirement** that you want to delete, or select the **textual requirement** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.


After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About rich text formatting

Blueprint provides you with the ability to create textual content using rich text formatting. In other words, you can perform many of the operations that you can perform using a word processing application. The rich text formatting features are available on the ribbon *Home* tab:




Here's a list of the rich text formatting features offered by Blueprint:

- Change font type, color, and size
- Make the font bold, italic, underline, subscript, superscript, strikethrough
- Apply highlighting to font
- Add a hyperlink
- Create a bulleted or numbered list
- Change the paragraph justification

RICH TEXT FORMATTING IN THE ARTIFACT LIST

Rich text formatting is displayed differently in the artifact list depending on the current mode. Here's an explanation of the different modes and the way rich text formatting is displayed:

- Edit in-place mode
 - all rich text formatting is displayed.



- Non-edit and wrap text disabled:
 - text is displayed as plain text.



- on hover, a tooltip displays a limited amount of rich text. Bullets and lists are not displayed in the tooltip.



- Non-edit and wrap text enabled:
 - displays a limited amount of rich text. For example: Highlighting, bullets and lists are not displayed.




Use cases

A *use case* describes an interaction between an actor and the system that yields an “observable result of value” to the actor.

Use cases are defined in order to specify all the different ways the system can be used. A complete set of use cases defines all behavior required of the system, effectively bounding the scope of the system without defining any of the system internals. Generally, use case steps are written using a structured narrative that is easy to understand. Use cases should be easy to follow and engaging for users, in order to ease the validation of each use case.

One of the benefits of creating use cases in Blueprint is the ability to simulate them. Use cases can be simulated using UI mockups to promote a clear understanding of the requirements and enhance the feedback provided by stakeholders.

Blueprint's [use case editor](#) provides you with the ability to easily create and edit use case artifacts. The use case editor looks like this:



Use Case Artifact Properties

By default, a use case artifact contains the following system properties:


- **Name:** Indicates the name of the **use case**.
- **Id:** Provides a unique identifier for the **use case**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Use Case Level:** Indicates the level of detail of the use case, measured from 1 (high level) to 10 (low level). Use cases can be automatically excluded from simulation or test case generation based on the **Use Case Level**.
- **Description:** Provides a description of the **use case**.

Your instance administrator can configure standard properties for each standard artifact type.

About the use case editor layout


The use case editor layout allows you to create use cases in either *text view*, *workflow view*, or *split view* (both *text view* and *workflow view*). Try out the different views and choose which ones works best for you. Various customizations are available for each view.

The use case editor looks like this:




USE CASES GROUP ON THE RIBBON VIEW TAB

There are a number of features on the *View* tab of the ribbon that allow you to customize the layout of the use case editor, as well as customize the look and feel of the diagram. The *Use Cases* group on the *View* tab looks like this:





The view and customization options include:

- **Views:** Allows you to select your desired view while working with a use case artifact. The view options are:
 - **Split:** Displays both the *text view* and the *workflow view* in the main content area.
 - **Text:** Displays the *text view* only, without the *workflow view*.
 - **Workflow:** Displays the *workflow view* only, without the *text view*.



Tip: To make more space available to view your artifact(s), you can collapse both the utility panel and the explorer panel by clicking the full screen button  (the lower rightmost corner of the window).

- **Full Text:** Displays the text of each use case step on a single line. This layout utilizes vertical space more efficiently, allowing you to view more use case steps in the main content area without scrolling.
- **Alternate Layout:** Displays the diagram in a way that uses less vertical space, at the expense of more overlapping connectors.

- **Curved Lines:** Displays the use case connectors using a curved line style. Curved lines are helpful if the use case has a number of alternative flows where the entrance and exit connectors overlap with other flow connectors. By switching to a curved line, the connector overlap is reduced.
- **Expand All:** Allows you to expand the alternate flows in *workflow view*. If you click **Expand All**, the alternate flows are displayed in full detail in the diagram.


Note: You can also use the *expand* buttons in *workflow view*  and *text view* .

- **Collapse All:** Allows you to collapse the alternate flows in *workflow view*. If you click **Collapse All**, the alternate flows are collapsed.

Note: You can also use the *collapse* buttons in *workflow view*  and *text view* .

USE CASES RIBBON TAB

When the use case editor is open, a *Use Cases* tab appears on the ribbon, providing you with various editing features. The *Use Cases* tab looks like this:



Step group:

- **Add Step:** Adds a new step to the use case, directly below the selected step.
- **Set Actor:** Associates an actor with the selected use case step, pre condition, or post condition.
- **Set UI Mockup:** Associates a UI mockup with the selected use case step(s).
- **Remove UI Mockup:** Removes a UI mockup from the associated use case step(s).
- **Include Use Case:** Associates a use case with the selected use case step. Including a use case in a step can be beneficial when a step is high level and you want to link the step to another use case that demonstrates the lower level steps that are required to complete that particular step. It also provides a way to reuse common functions across multiple use cases.
- **Move Step Up:** Moves the selected step(s) up one position in the use case.
- **Move Step Down:** Moves the selected step(s) down one position in the use case.
- **Delete Step(s):** Deletes the selected step(s).
- **Merge Steps:** Merges two or more selected use cases into a single use case step.



Flow group:

- **Add Alternate Flow:** Allows you to add an internal or external alternate flow.
 - **Add Internal Flow:** Adds an internal alternate flow to the use case. An *internal alternate flow* is an alternate flow defined within a use case.
 - **Add External Flow:** Adds an external alternate flow to the use case. An *external alternate flow* is an alternate flow that is included from an separate use case.
- **Set Start/Return Steps:** Allows you to set the start and return steps for an alternate flow.
- **Move Flow Up:** Moves the selected alternate flow up one position in the use case.
- **Move Flow Down:** Moves the selected alternate flow down one position in the use case.
- **Change External Use Case:** Changes the use case artifact of an external alternate flow to another use case artifact.

Simulate: Starts a simulation from the beginning of the use case.

Adding a use case

To add a use case artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **use case** icon .

After you have created a use case artifact, you may want to consider [adding actors](#) before [building your use case](#) content.

Building a use case

A use case consists of one or more flows, which are built using a sequence of use case steps. Every use case has a main flow that generally describes the main, or default, path through the use case.

Blueprint allows you to add alternate flows to your use cases. Alternate flows begin after a decision point, where the use case splits into two or more directions. An external alternate flow is the same as an internal alternate flow, except the flow is contained in a separate use case artifact.

Use case steps are typically associated with an actor, and are sometimes associated with UI mockups and other use cases. Actors are associated with use cases to clearly demonstrate the person or system that performs that task. Associating UI mockups with use case steps enhances the simulation experience, providing viewers with a richer and clearer understanding of the use case. Including a use case in a step can be beneficial when a step is high level and you want to link the step to another use case that demonstrates the lower level steps that are required to complete that particular step. It also provides a way to reuse common functions across multiple use cases.

KEY TERMS AND CONCEPTS

- A *use case* describes an interaction between an actor and the system that yields an “observable result of value” to the actor.
- An *actor* can be any person, role, organization, application, system, and so on, that interacts with the system being modeled.
- A *pre condition* lists the state(s) that must be true before the use case can begin.
- A *post condition* lists the state(s) that will always be true at the completion of the use case, regardless of the path or scenario followed.
- A use case *step* describes a discrete action performed by an actor or by the system being modeled.
- A *main flow* describes the typical set of steps that should occur in order to satisfy the post conditions of the use case.
- An *alternate flow* describes an optional series of steps that satisfies the post conditions of the use case.
- An *internal alternate flow* is an alternate flow defined within a use case.
- An *external alternate flow* is an alternate flow that is included from an separate use case.
- A *UI Mockup* is a prototype of a user interface in the system. UI mockups are effective on a standalone basis, but are even more powerful when they are viewed in simulations.


TYPICAL USE CASE CREATION

Use cases are typically created as follows:

1. Define the pre condition and the post condition.
2. Add new use case steps to define the main flow.
3. Set actors on the use case steps.
4. Include use cases in the use case steps, if applicable.
5. Add alternate flows, if applicable
6. Add UI mockups to the use case steps, to enhance the simulation experience.

USE CASE EXAMPLE

The following example shows a use case in *split view*, which includes both the *text view* and the *workflow view* in the main content area at one time.



Adding use case steps

A *use case* describes an interaction between an actor and the system that yields an “observable result of value” to the actor.

A use case *step* describes a discrete action performed by an actor or by the system being modeled.

Note: You can only add one use case step at a time.

To add a use case step:

1. Select a use case step.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.

2. Click **Add Step**.

Choose one of the following options to add a use case step:

- Click the **Add Step** button on the ribbon (*Use Cases* tab, *Step* group).
- Click the **Add Step** option on the context menu when you right-click an existing use case step.

The new step is added directly after the selected step.

Tip:

If you are using *text view*, you can easily add a new step by pressing the **Enter** key when your cursor is positioned on an existing use case step.

To add a line break, press **Shift+Enter**.

Deleting use case steps

You can delete use case steps using a variety of methods, depending on whether you are building your use case using *text view* or *workflow view*.

To delete a use case step:

1. Select the use case step(s) that you want to delete.
 - In *text view*, use your mouse to select the text of one or more use case step(s).
 - In *workflow view*, click a use case step. You can select multiple steps in *workflow view* by holding the **Ctrl** key and clicking multiple steps, or by drawing a box around a group of steps.

2. Click **Delete Step(s)**.

Choose one of the following options to delete the use case step(s):

- Click the **Delete Step(s)** button on the ribbon (*Use Cases* tab, *Step* group).
- Click the **Delete Step(s)** option on the right-click context menu.
- Click the **Delete** key on your keyboard.

Merging use case steps

Merging use case steps is useful whenever you want to combine multiple steps into one use case step. When you merge steps, the text from each step is preserved but combined into a single step. Blueprint allows you to merge two or more steps at one time.

To merge two or more use case steps:

1. Select two or more use case steps that you want to merge.
 - In *text view*, use your mouse to select the text of one or more use case step(s).
 - In *workflow view*, click a use case step. You can select multiple steps in *workflow view* by holding the **Ctrl** key and clicking multiple steps, or by drawing a box around a group of steps.
2. Click **Merge Steps**.

You can use the following buttons to merge use case steps:

- the **Merge Steps** button on the ribbon (*Use Cases* tab, *Step* group)
- the **Merge Steps** option on the right-click context menu

After you have successfully merged two or more use case steps, the text from both steps are merged into a single use case step.

Tip: In *textual view*, you can also merge two steps by pressing the **Backspace** key at the beginning of a step, or by pressing the **Delete** key at the end of a step.

Rearranging the order of use case steps and flows

While you are creating or editing a use case, you may need to move steps or flows up or down. Blueprint provides some easy ways to perform this task.

To move steps up or down within the flow:

1. Select the step(s) that you want to move.
 - In *text view*, use your mouse to select the text of one or more use case step(s).
 - In *workflow view*, click a use case step. You can select multiple steps in *workflow view* by holding the **Ctrl** key and clicking multiple steps, or by drawing a box around a group of steps.
2. Click **Move Step Up** or **Move Step Down**.

Choose one of the following options to move the step(s) up or down:

- Click the **Move Step Up** or **Move Step Down** button on the ribbon (*Use Cases* tab, *Step* group).
- Click the **Move Step Up** or **Move Step Down** option on the right-click context menu.

To move a flow up or down within the use case:

1. Select the flow that you want to move.
 - In *text view*, place the cursor on the text of an alternate flow.
 - In *workflow view*, click a use case step in the alternate flow.
2. Click **Move Flow Up** or **Move Flow Down**.

Choose one of the following options to move the step(s) up or down:

- Click the **Move Flow Up** or **Move Flow Down** button on the ribbon (*Use Cases* tab, *Flow* group).
- Click the **Move Flow Up** or **Move Flow Down** option on the right-click context menu.

Adding an actor to a use case step

An *actor* can be any person, role, organization, application, system, and so on, that interacts with the system being modeled.

Adding actors to your use case steps is beneficial because it helps to more clearly illustrate the interaction between the person (or abstract entity) and the system.

Note: You can only set actors on use case steps one at a time.


To add an actor to a use case step:

1. Select a use case step.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.
2. Click **Set Actor**.

Choose one of the following options to add an actor to a use case step:

- Click the **Set Actor** button on the ribbon (*Use Cases* tab, *Step* group).
- Click the **Set Actor** option on the right-click context menu.

After you have successfully added an actor, the name of the actor is included as a link in the use case step. You can click the actor link to view the actor details. Here's an example of the actor link in *workflow view*:



3: [User](#) enters credentials

Including a use case in a step

A use case *step* describes a discrete action performed by an actor or by the system being modeled. Including a use case in a step can be beneficial when a step is high level and you want to link the step to another use case that demonstrates the lower level steps that are required to complete that particular step. It also provides a way to reuse common functions across multiple use cases.

Example

Sam, a business analyst, is creating a series of use cases for a web application. All of the use cases require that the user logs into the system before using any other features.

Sam starts by creating a **Login** use case. She then *includes* that use case at the beginning of all other use cases, instead of duplicating the login steps.

When Sam realizes she must make a change to the Login use case, she only has to update one use case instead of 20.

To add a use case to a use case step:

1. Select a use case step.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.
2. Click **Include Use Case**.

You can use the following buttons to add a use case to a use case step:

- the **Include Use Case** button on the ribbon (*Use Cases* tab, *Step* group)
- the **Include Use Case** option on the right-click context menu

After you have successfully associated a use case with a step, the name of the included use case is displayed as a link in the use case step. You can click the use case link to view the details of the included use case. Here's an example of the included use case link in *workflow view*:



1: [Include UC43531: login](#)

Adding an internal alternate flow

An *internal alternate flow* is an alternate flow defined within a use case.

Alternate flows allow you to demonstrate the behavior of the system, given a particular condition. For example, the system will behave differently depending on whether the user clicks **Yes** or **No** after a confirmation dialog is displayed.

To add an internal alternate flow to a use case:

1. Select the step where you want the alternate flow to begin.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.
2. Click **Add Alternate Flow > Internal**.





Choose one of the following options to add an internal alternate flow:

- Click the **Add Alternate Flow** drop-down on the ribbon (*Use Cases* tab, *Step* group) and then select **Internal**.
 - Click the **Add Internal Flow** option on the right-click context menu.
3. Set the start and return steps.

You can use the following buttons to [set the start and return steps](#):

- the **Set Start/Return Steps** button on the ribbon (*Use Cases* tab, *Flow* group)
- the **Set Start/Return Steps** option on the right-click context menu

After you have added an alternate flow, a decision point  appears in *workflow view*. In *text view*, a new flow appears under the *Alternate Flows* heading.


In *workflow view*, you can expand and collapse the alternate flow using the *expand*  and *collapse*  icons. In *text view*, you can expand and collapse the alternate flow using the *expand*  and *collapse*  icons.

Note: Alternate flows are labeled the same way in both *text view* and *workflow view*. Conditions that are peers end in letters (example: 2a, 2b, and 2c). The regular steps in the flows end in numbers based on the condition. Therefore, condition 2a has steps labeled 2a1, 2a2 and so on.

Flow Conditions

The first step in an alternate flow is a condition. Also, the step in the main flow immediately after the decision point also becomes a condition. The text of the condition steps must indicate under what condition the main flow and the alternate flow will be exercised.

In the example below, the alternate flow is exercised in the event that an incorrect password is provided by the user:



Adding an external alternate flow

An *external alternate flow* is an alternate flow that is included from an separate use case.

Alternate flows allow you to demonstrate the behavior of the system, given a particular condition. For example, the system will behave differently depending on whether the user clicks **Yes** or **No** after a confirmation dialog is displayed. An external alternate flow is the same as an internal alternate flow, except the use case content is stored in a different (external) use case artifact.

To add an external alternate flow to a use case:

1. Select the use case step where you want the external flow to begin.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.

2. Click **Add Alternate Flow > External**.

Choose one of the following options to add an external alternate flow:

- Click the **Add Alternate Flow** drop-down on the ribbon (*Use Cases* tab, *Step* group) and then select **External Flow**
- Click the **Add External Flow** option on the right-click context menu

After you click the button, the *Select Use Case* dialog appears.

3. Select the use case you want to add.
 1. Search or browse for the **use case**.
 2. Click **OK**.





4. Set the start and return steps.

You can use the following buttons to set the start and return steps:

- the **Set Start/Return Steps** button on the ribbon (*Use Cases* tab, *Flow* group)
- the **Set Start/Return Steps** option on the right-click context menu

Read more about [Setting start and return steps](#).

After you have added an alternate flow, a decision point  appears in *workflow view*. In *text view*, a new flow appears under the *Alternate Flows* heading.


In *workflow view*, you can expand and collapse the alternate flow using the *expand*  and *collapse*  icons. In *text view*, you can expand and collapse the alternate flow using the *expand*  and *collapse*  icons.

Note: Alternate flows are labeled the same way in both *text view* and *workflow view*. Conditions that are peers end in letters (example: 2a, 2b, and 2c). The regular steps in the flows end in numbers based on the condition. Therefore, condition 2a has steps labeled 2a1, 2a2 and so on.

Flow Conditions

The first step in an alternate flow is a condition. Also, the step in the main flow immediately after the decision point also becomes a condition. The text of the condition steps must indicate under what condition the main flow and the alternate flow will be exercised.

In the example below, the external flow is exercised in the event that an incorrect password is provided by the user:



Changing an external use case

An *external alternate flow* is an alternate flow that is included from an separate use case. If you have added an external alternate flow to your use case, you can easily change it to a different external use case.

To change an external use case:

1. Select the external use case that you want to change.
 - In *text view*, place the cursor anywhere in the text of the external flow.
 - In *workflow view*, click a step in the external flow.
2. Click **Change External Use Case**

Choose one of the following options to add an external flow:

 - Click the **Change External Use Case** drop-down on the ribbon (*Use Cases* tab, *Flow* group).
 - Click the **Change External Use Case** option on the right-click context menu

After you click the button, the *Select Use Case* dialog appears.
3. Select the use case you want to add.
 1. Search or browse for the **use case**.
 2. Click **OK**.

Setting start and return steps

Setting the start and return steps is useful when you want an alternate flow to start from, or return to, a different step in the use case.

Alternate flows can start from any step in the use case, and can end in any step, the post condition, or exit.

To set the start and return steps:

1. Select an alternate flow.
 - In *text view*, place the cursor on the text of an alternate flow.
 - In *workflow view*, click a use case step in the alternate flow.

2. Click **Set Start/Return Steps**.

You can use the following buttons to open the *Set Start/Return Steps* dialog:

- the **Set Start/Return Steps** button on the ribbon (*Use Cases* tab, *Flow* group).
- the **Set Start/Return Steps** option on the right-click context menu.

3. Choose the start and return steps.

Use the drop-down options to set the *Start Step* and the *Return Step*. Alternate flows can start from any step in the use case, and can end in any step, the post condition, or exit.

4. Click **OK**.

After you have set the start and return steps, the step numbers are updated in *text view*, and the connectors are updated in *workflow view*.

Setting UI mockups on use case steps

A *UI Mockup* is a prototype of a user interface in the system. UI mockups are effective on a standalone basis, but are even more powerful when they are viewed in simulations. Associating UI mockups with use case steps enhances the simulation experience, providing viewers with a richer and clearer understanding of the use case.


To add a UI mockup to a use case step:

1. Select one or more use case step(s) that you want to associate with a UI mockup.
 - In *text view*, use your mouse to select the text of one or more use case step(s).
 - In *workflow view*, click a use case step. You can select multiple steps in *workflow view* by holding the **Ctrl** key and clicking multiple steps, or by drawing a box around a group of steps.

2. Click **Set UI Mockup**.


You can use the following buttons to set a UI mockup for use case steps:

- the **Set UI Mockup** button on the ribbon (*Use Cases* tab, *Step* group)
- the **Set UI Mockup** option on the right-click context menu

In *workflow view*, a *UI mockup*  indicator appears in the upper-left corner of the use case step after a UI mockup has been set. In *text view*, the *UI mockup* indicator appears beside the step on the left side. You can click the *UI mockup* indicator to view the associated UI mockup.

Removing a UI mockup from a use case step

A *UI Mockup* is a prototype of a user interface in the system. UI mockups are effective on a standalone basis, but are even more powerful when they are viewed in simulations.


When a UI mockup is associated with a use case, a UI mockup  indicator appears above the use case step in *workflow view*.

Note: You can only remove UI mockups from use case steps one at a time.

To remove a UI mockup from a use case step:

1. Select the use case step that is associated with the UI mockup you want to remove.
 - In *text view*, place the cursor on a use case step by clicking anywhere on the use case text.
 - In *workflow view*, click a use case step.
2. Click **Remove UI Mockup**.

Choose one of the following options to remove the UI mockup from the use case step:

- Click the **Remove UI Mockup** button on the ribbon (Use Cases tab, Step group).
- Click the **Remove UI Mockup** option on the right-click context menu.
- Click the **Remove UI Mockup** option that appears when you right-click the *UI mockup*  indicator in *workflow view*.

After you have removed the UI mockup, the UI mockup  indicator no longer appears above the step in *workflow view*.

Deleting a use case

To delete a use case:

1. Open the **use case** that you want to delete, or select the **use case** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About use case simulation

Overview

Envisioning what a feature or end product will look like can be challenging when you only have fragmented UI Mockups and requirements. Simulation can alleviate the issue of having many scattered requirements by presenting an interactive animation in which all details connect. A simulated use case is a visual animation, like a movie, that draws attention to the progress of a multi-layered scenario. The Blueprint simulation feature allows you to develop the relationships between requirements rather than focusing too much on the requirements as separate entities.

Example

Sam, a business analyst, has been collecting requirements from various stakeholders for an airline web site. She wants to discover the value her requirements can have together. She has created a use case that involves a customer checking in online and now she wants to explain the use case scenario to other stakeholders. In a meeting with developers, Sam walks through each step of the use case simulation on a projection screen. Starting now, the developers fully comprehend the functionality they are going to build. The simulation has sparked discussions about build planning, which propels the developers forward in their project's progress. In another meeting, Sam shows the use case simulation to sales representatives. One of the sales representatives suggests a piece of functionality that could be added to the use case, creating discussion about how the new functionality could better meet customers's needs. For the first time since the project began, stakeholders are able to understand the project and, as a result, contribute to its success and completion.

Simulation can help meet the unique needs of various teams. On its most basic level, use case simulation helps requirement authors explain their feature to stakeholders. Business analysts and developers can "walk through" simulated use cases together to verify if a feature works. Business analysts and higher management can watch use case simulations together to see if the functionality aligns with business goals. Simulating a use can help to identify and eliminate gaps in the requirements and the project as a whole, which is valuable to all stakeholders.

Simulating a use case

Note: Simulations only display changes that you have saved or published. If you need to modify an artifact, you can make changes to the artifact, save the changes, and then refresh the simulation.

To simulate a use case:


1. Click the ID of the use case artifact you want to simulate.
The use case artifact opens in the *main content area*.
2. Click the **Simulate** button (*Use Cases* tab).
The confirmation dialog appears.
3. Click **OK**.

The Blueprint Simulate window appears with your *Use Case Simulation* in the Explorer panel.

Navigating your Use Case Simulation

OVERVIEW

The use case steps appear in the Explorer panel to the left (under *Use Case Simulation*).




Tip: Click the arrows next to your use case to view the steps in the *Use Case Simulation*.

Use cases are typically navigated step-by-step, from pre condition (the beginning) to post condition (the end).


However, you can begin the simulation at whichever use case step you prefer. For more information about starting from a different point, see [Starting the simulation at another step](#).

NAVIGATION MARKERS


The use case step you have currently selected has an orange outline:



When you select a use case, the use case, and all of its steps, become green:



Use case steps you have already viewed are highlighted in the *Use Case Simulation*:



CHANGING THE SCOPE OF THE USE CASE SIMULATION

The scope controls allow you to show any connected external flows and/or included use cases in the simulation.

You can alter the scope of the *Use Case Simulation* by using the following controls (*Home* tab, *Scope* group):

- **Simulate Related Use Cases** (selected by default): when selected, the chain of included use cases is added to the scope of the simulation. When deselected, only the main use case is simulated.
- **Use Case Level:** allows you to control the degree to which any included use cases and external flows are shown. You can select a higher number of connected levels to show, or you can select a low number to hide included use cases.

Note: All levels of included use cases are auto-detected when the **Simulate Related Use Cases** check box is selected.




USING THE NAVIGATION CONTROLS

To navigate through the *Use Case Simulation*, use the buttons in the *Navigation Controls* group (*Home* tab):

- To control the progression of steps, click the **Next Step** button whenever you want to move to the next step.
- To watch a computerized navigation of the use case, click the **Start Automatic Navigation** button.

Note: Automatic Navigation stops when it reaches any step that is connected to alternate flows and requires actor input. For more information about actors interacting with alternate flows, see [Actor-system interaction and alternate flows](#).

- To restart the viewing, click the **Start Over** button at any time.
After clicking **Start Over**, the orange outline reappears on the first step.
- To navigate to the previous use case step, click the **Previous Step** button.




STARTING THE SIMULATION AT ANOTHER STEP

The use case simulation starts at the pre condition and then progresses sequentially but you can choose to start the simulation at any step you like.

Note: The **Simulate Related Use Cases** check box must be selected in order to start the simulation from any included use case step.

To start a simulation at another step:

- Right-click the step you want the simulation to start with and then click **Start Simulation from Here**.




An orange outline appears around the step, signifying that it is selected. The step details appear in the *main content area*.

ACTOR-SYSTEM INTERACTION AND ALTERNATE FLOWS

Blueprint Simulate allows you to test use case steps that require flow selection from an actor. Blueprint Simulate puts you in the role of the actor, navigating the scenario you have created. You, playing the actor, can choose one of the available flows in order to progress with the scenario (that is, to progress to the next step).

Example

Sam, a business analyst, wants to simulate a use case that involves checking in online for an airline flight. To begin the simulation, she clicks the **Start Automatic Navigation** button. The first use case step (that is, the main check-in web page displaying all flights) appears for a set number of seconds. Then, automatically, the next step appears, which requires the customer (actor) to select a flight for check-in. Sam must select a flight from the list and click the **Check In** button to progress to the next step.



Using keyboard shortcuts during use case simulation

Blueprint offers a number of keyboard shortcuts that allow you to conveniently perform various operations and navigate your *Use Case Simulation* using your keyboard instead of your mouse. Using keyboard shortcuts can be

helpful when presenting a use case simulation to stakeholders or other individuals. The controls provide an easy way to navigate to other steps in the simulation and to refresh artifacts, letting you focus on the content matter you are presenting.

This article outlines keyboard shortcuts for both basic and navigational operations in *Use Case Simulation*. Many of the operations listed in this article are also accessible on the application ribbon.

Note: Some keyboard shortcuts are currently unavailable for Internet Explorer, such as the font editing, refresh and help operations.

KEYBOARD SHORTCUTS FOR FONT EDITING OPERATIONS

Firefox and Chrome Keyboard Key	Operation	Result / Effect
CTRL + B	Make the selected text bold	You can apply the bold operation to text in the Comment field within the <i>Utility Panel</i> .
CTRL + I	Italicize the selected text	You can apply the italicize operation to text in the Comment field within the <i>Utility Panel</i> .
CTRL + U	Underline the selected text	You can apply the underline operation to text in the Comment field within the <i>Utility Panel</i> .

KEYBOARD SHORTCUTS FOR SIMULATION NAVIGATION

Firefox and Chrome Keyboard Key	Internet Explorer Keyboard Key	Operation	Result / Effect
F8	F8	Start automatic navigation mode	Starts Auto Navigation mode at the selected use case step. When Auto Navigation mode is started, each use case step appears for the number of seconds specified in the Auto-Nav Interval setting. Note: Automatic Navigation stops when it reaches any step that is connected to alternate flows and requires actor input. For more information about actors interacting with alternate flows, see Actor-system interaction and alternate flows .
F8	F8	Pause automatic navigation mode	Pauses Auto Navigation mode at the selected use case step. To resume automatic navigation, press F8 again.
F7	SHIFT + F9	Navigate to the previous use case step	The previous use case step is selected in the <i>Explorer</i> panel and the step details appear in the bottom pane.

Firefox and Chrome Keyboard Key	Internet Explorer Keyboard Key	Operation	Result / Effect
F9	F9	Navigate to the next use case step	The next use case step is selected in the <i>Explorer</i> panel and the step details appear in the bottom pane.
CTRL + SHIFT + F8	CTRL + SHIFT + F8	Start over from the beginning	The first use case step is re-selected in the <i>Explorer</i> panel and the step details appear in the bottom pane.

KEYBOARD SHORTCUT TO REFRESH


Firefox and Chrome Keyboard Key	Operation	Result / Effect
CTRL + F5	Refresh all artifacts	Reloads the use case simulation with the most recent version of the use case artifact and any related artifact(s).

KEYBOARD SHORTCUTS TO ACCESS HELPFUL INFORMATION

Firefox and Chrome Keyboard Key	Internet Explorer Keyboard Key	Operation	Result / Effect
F1	-	Get help using Blueprint	The <i>Blueprint Help</i> web site opens in another tab. You can enter the keyword(s) for the issue you are experiencing in the search field and press ENTER.
CTRL + SHIFT + 1	CTRL + SHIFT + 1	Opens keyboard shortcuts pop-up	The <i>Keyboard Shortcuts</i> dialog box appears with a list of all of the <i>Home</i> tab shortcuts mentioned in this table.

VIEWING A LIST OF SHORTCUTS

To view a list of shortcuts within simulation, press CTRL + SHIFT + 1.



UI mockups

A *UI Mockup* is a prototype of a user interface in the system. UI mockups are effective on a standalone basis, but are even more powerful when they are viewed in simulations.

UI Mockup Properties



By default, a UI mockup artifact contains the following system properties:

- **Name:** Indicates the name of the **UI mockup**.
- **Id:** Provides a unique identifier for the **UI mockup**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Width:** Indicates the width of the **UI mockup**, measured in pixels. The maximum size is 7000 pixels.
- **Height:** Indicates the height of the **UI mockup**, measured in pixels. The maximum size is 7000 pixels.
- **Description:** Provides a description of the **UI mockup**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a UI mockup

To add a UI mockup artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **UI mockup** icon .

Deleting a UI mockup

To delete a UI mockup:

1. Open the **UI mockup** that you want to delete, or select the **UI mockup** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Previewing a UI mockup

Blueprint allows you to preview how your UI mockup would function in a use case simulation. There is no need to save your UI mockup and then simulate your changes in a use case. You can preview the final product with the click of a button.

Interactive and non-interactive widgets

UI mockups can contain interactive widgets in addition to non-interactive widgets.

An *interactive widget* is any UI mockup shape that can be interacted with. For example, you can click an interactive widget, select options from a widget or type text in a widget.

Example

Jorges, a business analyst, adds a **Login** button to his UI mockup of an online log-in page. When his use case is simulated, viewers can click the **Login** button to go to the next step in the simulation.

A *non-interactive widget* can fall into one of two categories: shapes that model UI elements, like browsers, and shapes that call out system behavior. For example, a callout widget can be used to explain a new feature and then can be hidden on use case steps when the callout does not need to be seen.

Types of interactive widgets include but are not limited to:

- Button
- Checkbox
- Dropdown Button
- Dropdown List
- Hyperlink
- Slider


- Text Area
- Text Box

There are two ways to interact with UI mockup widgets: launching a simulation of a use case and viewing a preview of the UI mockup.

To preview your UI mockup:

1. Click the **Preview** button (*UI Mockup* tab).

The *Preview Mode* bar appears at the top of your UI mockup.



If you have added any interactive widgets, you can test widget functionality similarly to how viewers of a use case simulation would interact with your UI mockup.

2. To exit *Preview* mode and return to editing mode, click the **Preview** button.

About screen captures

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

The *Screen Capture* feature allows you to quickly and easily take a screen capture of an application running on your computer and then insert it into a Blueprint artifact. Screen captures are automatically resized to fit the canvas if the image is too large to fit. Whenever Blueprint resizes screen captures, the aspect ratio is preserved.



Example

Matt, a business analyst, plans to make some changes to an existing web page. He starts by creating a new UI mockup artifact. He then uses the screen capture feature to quickly add a screen capture of the existing web page to the UI mockup. At this point, Matt can take advantage of the UI mockup widgets to create a rich visual representation of the new user interface.


APPLICABILITY

You can add a screen capture to any Blueprint artifact that supports images, including:

- UI mockups
- Use case diagrams
- Generic diagrams

When the *Screen Capture* feature is applicable, a **Screen Capture**  button appears on artifact editor contextual tab on the ribbon. For example, if you open a generic diagram, the **Screen Capture**  button appears on the ribbon (*Generic Diagram* tab, *Image* group). If you open an actor or document artifact, this button is not available.

ADDING A SCREEN CAPTURE TO AN ARTIFACT

When you click the **Screen Capture**  button, Blueprint displays a list of all application windows that are open (but not minimized) on your computer.

To add a screen capture to an artifact:


1. Open the application from which you want to take a screen capture.
2. Leave the application running and switch to Blueprint.

Important: Ensure the application window does not become minimized when you switch to Blueprint.

3. Open the artifact that you want to add a screen capture to.

The *Screen Capture* feature is only available in artifacts that support the insertion of images. Refer to the [Applicability](#) section to learn more about support for this feature.

4. Click the **Screen Capture** button on the ribbon.

The **Screen Capture**  button is located on artifact editor contextual tab (example: *Generic Diagram* tab) in the *Image* group.

After you click the button, the application windows are displayed. If you are using Windows 7, the windows are displayed as thumbnail images. If you are using an older version of Windows, the windows are displayed in a list of window titles.

5. Click the application window that you want to capture.

After you click the application window that you want to capture, the screen capture is taken and automatically inserted into the artifact.

Glossary artifacts

A glossary artifact is a compilation of terms and definitions. Glossary terms can be linked from other artifacts, providing readers with easy access to definitions.

Maintaining a glossary is one of the simplest ways to reduce misunderstanding by encouraging project members to use a common vocabulary. Blueprint allows you to create multiple glossaries. You can then merge terms between glossaries to create a repository of common words. Blueprint's glossary artifact provides you with an easy way to manage and reference definitions for acronyms, business terms, and technical terms.

Glossary Artifact Properties



By default, a glossary artifact contains the following system properties:

- **Name:** Indicates the name of the **glossary**.
- **Id:** Provides a unique identifier for the **glossary**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Description:** Provides a description of the **glossary**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a glossary

To add a glossary artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **glossary** icon  .

Deleting a glossary

Note: If you delete a glossary, all terms that are linked from other artifacts will continue to reference a read-only version of the glossary.

To delete a glossary:

1. Open the **glossary** that you want to delete, or select the **glossary** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Adding a new term directly to the glossary

1. Open a glossary artifact.
2. Right-click and select **Add Term**. A new row appears in the table.
3. Type the name of the term and definition into the *Term* and *Definition* columns.
The terms and definitions are now sub-artifacts of the glossary.

Adding a new glossary term from another artifact

You can easily add a new term to a glossary while working on any artifact in the system.

Notes

When you use the **Add to Glossary** feature, the term is added to the glossary, but a [link to the glossary term](#) is not automatically included in the artifact that you are working on.

After the new term is added, you still have to [edit the glossary to provide a definition for the term](#).

To add a new glossary term while working on another artifact:

1. Highlight the text that you want to add as a term to the glossary.
2. Click **Add to Glossary**.
 1. right-click and select **Add to Glossary**.
The *Add to Glossary* dialog appears.
3. Select the glossary you want to contain the new term.
 1. Search or browse for the **glossary**.
 2. Click **OK**.

A dialog appears to notify you that the term was added successfully.


After you have added the new glossary term, you may want to [link the term to some text in your artifact](#). You may also want to [edit the glossary term](#) to provide a definition for the new term.

Linking to an existing glossary term from other artifacts

Linking to a glossary term is referred to as a glossary reference. After you have created a glossary reference, you can point to the terms to view the definition inline.

1. Open the artifact and highlight the text that you want to link to a glossary term.
2. Click **Add Glossary Reference**.
 1. Right-click and select the **Add Glossary Reference** option.
The *Add Glossary Reference* dialog appears.
3. Select the glossary term.
 1. Search or browse for the glossary term.
 2. Click **OK**.

After you have added a glossary reference, the term is displayed as a link. If you hover on the link, the definition is displayed as follows:



Editing a glossary term

1. Open the glossary that contains the term that you want to edit.
2. Double-click the term or definition that you want to edit. Edit mode is now activated, allowing you to make changes to the existing content.

Deleting a glossary term

Note: After you delete a glossary term, the definition is no longer available from any artifacts that are linked to the term.

1. Open the glossary artifact that contains the term you want to delete.
2. Right-click the term you want to delete and select **Remove Term**.

About Storyboards

A *storyboard artifact* provides a quick way to depict scenarios of a user progressing through the screens of a system.

Storyboards can show screen sequencing and branching to different screens. Storyboards contain frames, that in turn can contain UI mockup artifacts. Frames can act as placeholders for future screens, and can also provide descriptive text of screen content and interaction. Storyboards tend to be used to communicate user interface requirements at a high level, as opposed to use cases which tend to communicate detailed actor–system interaction.

Storyboard Artifact Properties



By default, a storyboard artifact contains the following system properties:

- **Name:** Indicates the name of the **storyboard**.
- **Id:** Provides a unique identifier for the **storyboard**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Width:** Indicates the width of the **storyboard**, measured in pixels. The maximum size is 7000 pixels.
- **Height:** Indicates the height of the **storyboard**, measured in pixels. The maximum size is 7000 pixels.
- **Description:** Provides a description of the **storyboard**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a storyboard

To add a storyboard artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **storyboard** icon  **Storyboard**.

Deleting a storyboard

To delete a storyboard:

1. Open the **storyboard** that you want to delete, or select the **storyboard** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Actors

An *actor* can be any person, role, organization, application, system, and so on, that interacts with the system being modeled.

After you have created actor artifacts, you can set one or more actors for each step in a use case. The purpose of creating actor artifacts is to include them in use case steps.

Actor Artifact Properties

By default, an actor artifact contains the following system properties:

- **Name**: Indicates the name of the **actor**.
- **Id**: Provides a unique identifier for the **actor**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.
- **Inherits From**: If the actor is inherited from another actor (that is, a *parent*), this property indicates the name and ID of the *parent* actor.



- **Image:** Indicates the filename of the actor image.
- **Description:** Provides a description of the **actor**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding an actor artifact

An *actor* can be any person, role, organization, application, system, and so on, that interacts with the system being modeled.

To add an actor artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **actor** icon  .

After you have added a new actor artifact, you may want to [set actor inheritance](#) or [set a custom image](#) for the actor. You may also want to [associate the actor with a use case step](#).

Setting and removing actor inheritance

Actor inheritance allows you to establish relationships between actors.

Note: When you set actor inheritance, a relationship is established, but no properties are shared between the actors. Actor Inheritance creates a special relationship between actors. Property values of the parent actor are not automatically set as properties for the child.

Example

Sally, a business analyst, has created two actors: **Part Time Employee** and **Full Time Employee**. Some of her use case steps can be performed by both actors. Instead of including both actors in each use case step, Sally creates a third actor called **Employee**. She then modifies the two existing actors and sets the *Inherits From* property to the new **Employee** actor. Now, Sally can simply include the new **Employee** actor in the use case steps because the other actors inherit from the **Employee** actor.

To set the inheritance of an actor:

1. Open an actor artifact.
Click the artifact ID link of the **actor** artifact you want to open.
2. Click the **Edit** link located under the *Inherits From* property.
The *Select Actor* dialog appears.
3. Search or browse to select an actor.
4. Click **OK**.
The **OK** button is only accessible if you have selected an actor artifact.

After you have set the `Inherits From` property, Blueprint displays the ID and name of the actor:

Properties	
Name	Online Banking Customer
Id	AC4668429
Type	Actor
Inherits From	AC4668428 :Customer Edit / Remove

You can also view the actor inheritance on the *Relationships* tab in the utility panel if you select **Other** in the **Traces** drop-down:

» Utility Panel			
AC4668428: Customer			
Add Trace			Relationships
			Traces
			Parent / Child
			Other
Actor Inherits			
←	AC4668429	Online Banking Customer	✓
←	AC4668430	Tele-Banking Customer	Online Banking

To remove the inheritance of an actor:

1. Open an actor artifact.
Click the artifact ID link of the **actor** artifact you want to open.
2. Click the **Remove** link located beside the `Inherits From` property.

Setting and removing an actor image

When you set a custom image for an actor, the image appears in simulations when the actor is set on a use case step. This provides viewers with a visual indication of what actor is performing that particular step in the use case.

To set a custom image for an actor:

1. Open an actor artifact.
Click the artifact ID link of the **actor** artifact you want to open.
2. Click the **Edit** link located under the `Inherits From` property.
After you click the link, the *Open* dialog appears.
3. Select the image file that you want to associate with the actor.

After you have set the actor image, Blueprint displays the picture in the rectangular box above the **Edit** link.

To remove a custom image for an actor:

1. Open an actor artifact.
Click the artifact ID link of the **actor** artifact you want to open.
2. Click the **Remove** link located under the image.

Deleting an actor artifact

Note: After you delete an actor artifact, the artifact can only be accessed in read-only mode. Any use case steps that are associated with an actor will link to the read-only version of the deleted artifact.

To delete an actor:

1. Open the **actor** that you want to delete, or select the **actor** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Business process diagrams

Business process diagram artifacts provide a clear visual representation of requirements involving sequence, flow, branching, conditions, etc.

Business Process Diagram Artifact Properties



By default, a business process diagram artifact contains the following system properties:

- **Name:** Indicates the name of the **business process diagram**.
- **Id:** Provides a unique identifier for the **business process diagram**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Width:** Indicates the width of the **business process diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Height:** Indicates the height of the **business process diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Description:** Provides a description of the **business process diagram**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a business process diagram

To add a business process diagram artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **business process diagram** icon  Business...

Deleting a business process diagram

To delete a business process diagram:

1. Open the **business process diagram** that you want to delete, or select the **business process diagram** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About Generic Diagrams

A *generic diagram* refers to a diagram that is created using Blueprint's Generic Diagram Editor. With the Generic Diagram Editor, you can draw free form diagrams, where the only limitation is your imagination.

Generic diagrams can be used for example to communicate:

- Context, scope, boundaries, and system interfaces.
- Structure, components, and deployment.
- States, sequence, and timing.
- Any form of requirement that is not already better expressed using one of the other artifact editors in Blueprint.

Generic Diagram Artifact Properties

By default, a generic diagram artifact contains the following system properties:



- **Name**: Indicates the name of the **generic diagram**.
- **Id**: Provides a unique identifier for the **generic diagram**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.
- **Width**: Indicates the width of the **generic diagram**, measured in pixels. The maximum size is 7000 pixels.

- **Height:** Indicates the height of the **generic diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Description:** Provides a description of the **generic diagram**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a generic diagram

To add a generic diagram artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **generic diagram** icon .

Deleting a generic diagram

To delete a generic diagram:

1. Open the **generic diagram** that you want to delete, or select the **generic diagram** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About Domain Diagrams

A *domain diagram* is generally used for problem analysis. A domain diagram shows the major pieces of information (entities), what they're composed of (elements), and how the information is related to each other. It uses relationship notation similar to Entity Relationship Diagrams (ERDs) used to model data schemas. Domain diagrams are sometimes referred to as domain models, information diagrams, information models, or conceptual data models.

Domain Diagram Artifact Properties

By default, a domain diagram artifact contains the following system properties:

- **Name:** Indicates the name of the **domain diagram**.
- **Id:** Provides a unique identifier for the **domain diagram**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Width:** Indicates the width of the **domain diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Height:** Indicates the height of the **domain diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Description:** Provides a description of the **domain diagram**.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a domain diagram

To add a domain diagram artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **domain diagram** icon  Domain....

Deleting a domain diagram

To delete a domain diagram feature:

1. Open the **domain diagram** feature that you want to delete, or select the **domain diagram** feature in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.


After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About use case diagrams

Use case diagrams display relationships between use cases and actors in the system.

Tip: To make more space available to view your artifact(s), you can collapse both the utility panel and the explorer panel by clicking the full screen button  (the lower rightmost corner of the window).

Use Case Diagram Artifact Properties

By default, a use case diagram artifact contains the following system properties:

- **Name:** Indicates the name of the **use case diagram**.
- **Id:** Provides a unique identifier for the **use case diagram**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Width:** Indicates the width of the **use case diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Height:** Indicates the height of the **use case diagram**, measured in pixels. The maximum size is 7000 pixels.
- **Show Conditions:** Indicates whether or not conditions are shown.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a use case diagram

To add a use case diagram artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **use case diagram** icon .

Deleting a use case diagram

To delete a use case diagram:

1. Open the **use case diagram** that you want to delete, or select the **use case diagram** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Document artifacts

A *document* artifact allows you to upload a file and then reference that file from multiple artifacts.

Document artifacts are different than file attachments. Document artifacts can be referenced from multiple artifacts by adding it as a document reference to other artifacts in the utility panel *files* tab. File attachments are also added in the *files* tab of the utility panel and are associated with a single artifact. Refer to [File attachments and document references](#) for more information.

Example

Pauline, a regulatory analyst, has asked business analysts to adhere to a number of standards while gathering requirements for the system. She creates a new document artifact and uploads the standards document to the artifact.

Gabrielle, a business analyst, modifies a use case so it adheres to the applicable standards. She adds a document reference to her use case artifact so other users will understand the rationale for the changes. She also adds a comment to the use case artifact to explain the reason for the modifications.

Document Artifact Properties

By default, a document artifact contains the following system properties:



- **Name:** Indicates the name of the **document**.
- **Id:** Provides a unique identifier for the **document**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Description:** Provides a description of the **document**.
- **File:** Provides the name of the uploaded file.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a document artifact

A *document* artifact allows you to upload a file and then reference that file from multiple artifacts.

To add a document artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **document** icon  Document.

After you have added a new document artifact, you will probably want to [upload a file](#).

Uploading a file to a document artifact

A *document* artifact allows you to upload a file and then reference that file from multiple artifacts.

After you [create a document artifact](#), you can upload a document file to the artifact. Each document artifact can contain a single document file. However, if a file already exists, you can upload a new file to replace the existing file. You can also use the *files* tab in the utility panel to upload multiple [file attachments](#) and [document references](#) to a document artifact.

1. Open a document artifact.

Click the artifact ID link of the artifact you want to open.

2. Click **Attach a File** or **Replace**.

The **Attach a File** link is only displayed if a file has not yet been uploaded. The **Replace** link appears after a user has uploaded a file. The **Replace** link allows you to upload a new file to replace the existing file. After you click one of the links, the *Open* dialog appears.

3. Select the file you want to upload and then click **Open**.

By default, the file selection window only displays **DOCx Files (.docx)** files. To select a different file type, click the drop-down and select a different type, or select **All files**.

4. Save or publish your changes to upload the file.


The file is uploaded from your computer to Blueprint. This may take some time depending on the size of the file you are uploading.

Note: Blueprint enforces a maximum file size for document uploads. The maximum file size is configurable by your project administrators.

Note: You must publish the artifact before your changes are viewable by other users.

After you upload a document file, you may want to add a textual summary of the file to the *Description* field. The document artifact *Name* is automatically replaced with the name of the document you uploaded, but Blueprint allows you to change the name, if required. The *File* field is also replaced with the name of the document, but you cannot change this value unless you rename the file on your computer and upload it again.

After you upload a file, you can click the **Download** link to download or open the file. You can also click **Replace** to upload a new file to replace the existing file:



Note: If you are using Internet Explorer 8, you must enable the *automatic prompting for file downloads* security setting before you can download the file from Blueprint. To enable this setting, click **Tools > Internet Options > Security > Custom level... > Downloads** and then enable the **Automatic prompting for file downloads** option.

Deleting a document artifact

To delete a document:

1. Open the **document** that you want to delete, or select the **document** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

User stories

A *user story* is a type of requirement used in agile development that contains brief, high-level information. User stories express a need for a new capability and are often written in the language of the end user interacting with the software.

User stories can be useful when you need to create a requirement that is not too detailed and can be adaptive to change. User stories are typically written with the goal of identifying a business value.

User stories, like all other artifacts, can be organized in a hierarchy and are often children of a higher-level *epic* artifact. You can also attach files to your user stories and trace your user stories to other artifacts.

User Story Artifact Properties



By default, a user story artifact contains the following system properties:

- **Name**: Indicates the name of the **user story**.
- **Id**: Provides a unique identifier for the **user story**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.
- **Acceptance Criteria**: Provides the criteria or goals the user story must meet to be completed.
- **Story Points**: Provides a detailed estimation of work effort.
- **TShirt**: Provides a brief, high-level estimation of work effort.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a user story

To add a user story artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **user story** icon  *User Story*.

Deleting a user story

To delete a user story:

1. Open the **user story** that you want to delete, or select the **user story** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Epics

An *epic* artifact is a large user story that can be separated into smaller user stories.

Once an epic artifact has been captured, it is often used as a parent artifact for smaller user story artifacts.

To support your existing business processes and standards, instance administrators can customize the set of requirement types and create other standard properties as needed.

Epic Artifact Properties



By default, an epic artifact contains the following system properties:

- **Name**: Indicates the name of the **epic**.
- **Id**: Provides a unique identifier for the **epic**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.
- **TShirt**: Provides a brief, high-level estimation of work effort.

Your instance administrator can configure standard properties for each standard artifact type.

Adding an epic

To add an epic artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **epic** icon .

Deleting an epic

To delete an epic:

1. Open the **epic** that you want to delete, or select the **epic** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

 - on the ribbon (*Home* tab, *Artifacts* group).
 - on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.
3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Themes

A *theme* broadly describes a goal, new capacity or area of focus within a roadmap.

Identifying themes first can help you prioritize larger goals before identifying smaller details related to the release. Once themes have been captured, they are often used as parent artifacts for user stories and epics.

Theme Artifact Properties



By default, a theme artifact contains the following system properties:

- **Name**: Indicates the name of the **theme**.
- **Id**: Provides a unique identifier for the **theme**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a theme

To add a theme artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **theme** icon .

Deleting a theme

To delete a theme:

1. Open the **theme** that you want to delete, or select the **theme** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Features

A *feature* is a service that provides value to a customer by fulfilling their needs. Feature artifacts can be used as high-level categories to organize other artifacts, such as epics and user stories.

To support your existing business processes and standards, administrators can customize the set of requirement types and create other properties as needed.

Feature Artifact Properties

By default, a feature artifact contains the following system properties:

- **Name**: Indicates the name of the **feature**.
- **Id**: Provides a unique identifier for the **feature**. The Id cannot be modified.
- **Type**: Indicates the type of artifact.
- **MoSCoW**: Identifies the importance of the feature to the release.

A feature can have one of the following priorities:



- **Must**: The feature is critical to the release.
- **Should**: The feature is high priority.
- **Could**: The feature is desired but not necessary.

- *Won't*: A requested feature that will not be included in the current phase but might appear in a future phase.
- *TShirt*: Provides a brief, high-level estimation of work effort.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a feature

To add a feature artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **feature** icon .

Deleting a feature

To delete a feature:

1. Open the **feature** that you want to delete, or select the **feature** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.
2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

Scenarios

A *scenario* is an example of how a person or organization interacts with a system.

Scenarios can be useful when you need to add context to a requirement by creating an example.

Scenarios, like all other artifacts, can be organized in a hierarchy and are often children of a higher-level *epic* or *user story* artifact. You can enhance your scenario by taking advantage of rich text formatting. You can also attach files to your scenarios and trace your scenarios to other artifacts.

To support your existing business processes and standards, instance administrators can customize the set of requirement types and create other standard properties as needed.

Scenario Artifact Properties



By default, a scenario artifact contains the following system properties:

- **Name:** Indicates the name of the **scenario**.
- **Id:** Provides a unique identifier for the **scenario**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.

Your instance administrator can configure standard properties for each standard artifact type.

Adding a scenario

To add a scenario artifact:

1. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
2. Select **Child Artifact**.
3. Click the **scenario**  icon.

Deleting a scenario

To delete a scenario:

1. Open the **scenario** that you want to delete, or select the **scenario** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.


3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About rich text tables

In Blueprint, you can create tables in any artifact field that supports rich text formatting. For example:

- *Description* fields
- Custom properties that support rich text
- *Comment* fields
- Text areas of diagrams



When you create a table, the *Layout and Styling* tab appears on the ribbon with table styling options to choose from.

To change the layout of your table, one or more table cells must be selected so that the *Layout and Styling* tab appears with styling commands.

Copying and pasting rich text tables to and from other applications

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

To copy and paste rich text tables from Blueprint to other applications, and vice-versa, you need to have *elevated in-trust browser* enabled (*Profile Options* menu). For more information about enabling elevated trust-in browser, see [About elevated trust in-browser](#).


Copying tables from Blueprint and pasting in Microsoft Office documents

When you copy a table from Blueprint and paste in a Microsoft Office program, like Word or Excel, any rich text formatting in the table is preserved.

Copying tables from Microsoft Office documents and pasting in Blueprint

When you copy a table from Microsoft Word or Excel and paste in Blueprint, any rich text formatting that is supported in Blueprint is preserved.

For example, when you copy a table with bold header font from Microsoft Word and paste it in Blueprint, the table's bold formatting is preserved (see image below). However, any font family in the Word table that is not supported in Blueprint is not preserved when pasting into Blueprint.



Adjusting the height of a cell


You can customize cells to appear with specified heights or with an automatically selected height. The automatically selected height adjusts the height so there is always enough room for the contents inside.

To change the height of a cell:

1. Select the cell for which you want to adjust the height.
2. Click the **Height** field (*Layout and Styling* tab, *Cells* group).

The cell height menu appears.

3. Select **Auto** if you want Blueprint to adjust the height automatically, or select **px** if you want to define the height yourself.



4. In the *Height* field, specify the pixel height for your cell.

The new height of your cell appears in your table, affecting any cells within the same row.

Adjusting the width of a table

You can adjust the width of a cell, a table column, a table row or an entire table.

To adjust the width of an entire table or cell(s):


1. Select the cell(s), the table column or the table row you want to alter.

Example

Selecting a table's rightmost column:



2. Click one of the following **Width** fields:



To change the width of an entire table: click after the number in the **Width** field in the *Table* group.


To change the width of one or more cell(s): click after the number in the **Width** field in the *Cell* group.

3. Choose a width format.

To choose the automatic width, click **Auto**.

To specify width in pixels, click **px**.

To specify width in percentage, click **%**.



4. Enter the new width in the **Width** field (*Layout and Styling* tab).

The cell(s) you have selected are resized to their new width.

Changing the border styling (color and weight) of a table or cell

Important: Border weight is only applied after selecting the border type. For example, if you select a border weight of 3 pt, the change is not applied until after you click **All Borders**.


To change the border of a table or cell:

1. Select the cells containing the borders you want to change.
2. Select your border color.
Click **Border Color** and then click the new color of your border (*Layout and Styling* tab, *Table Styling* group).
3. Select your border weight.
Click the **Borders** button, select **Weight** and then click the border weight you want (*Layout and Styling* tab, *Table Styling* group).

Note: The changes are not applied until the next step.

4. From the *Borders* menu, select your border type.

The border types you can choose from are specific to the sides of the border(s).



Your new border styling appears on your table or cell(s).


Deleting cells in a table

To delete cells:


1. Select one or more cell(s), columns or rows in a table.

Example

Selecting a table's rightmost column:



2. Click the **Delete** button and then click the corresponding command (*Layout and Styling* tab, *Rows & Columns* group).



To delete the selected cell(s): click **Delete Cells**.


To delete selected column(s): click **Delete Columns**.

To delete selected row(s): click **Delete Rows**.

To delete the entire table: click **Delete Table**.

The cells you have selected have been deleted.

You can also right-click the cell, table, column or row you want to delete, and the following menu allows you to click a corresponding command:




Inserting a new row or column

To insert a new row or column:

1. Select a cell in the table.
2. Click one of the following buttons from the *Layout* tab (*Rows & Columns* group):

To insert a new row: click **Insert Above** or **Insert Below**.

To insert a new column: click **Insert Left** or **Insert Right**.



Your table now has the row or column you inserted.

Merging and splitting cells

Merging cells allows you to have a different cell structure on each row or column. After you perform a merge, you can split the cells to restore the original cell structure.

Merging cells

You can merge two or more cells in a row or column into one cell.

To merge cells in a table:

1. Select the cells that you want to merge in your table.

Example

Selecting a table's rightmost column:

--	--	--

2. Click the **Merge Cells** button (*Layout and Styling* tab, *Merge* group).

The selected cells merge into one cell.

Splitting cells to undo a merge

The **Split Cells** button allows you to conveniently undo a cell merge at any time.

To undo a cell merge:

1. Select the cell that you merged.
2. Click the **Split Cells** button (*Layout and Styling* tab, *Merge* group).

The cells are restored to their original structure, reversing the merge.

Reusing requirements artifacts


Overview

Blueprint allows you to reuse requirements artifacts that have a standard artifact type.

Reusing artifacts can help you achieve the following business goals:

- Accelerate requirements delivery by leveraging resources that already exist
- Maintain consistency and follow standards in releases and projects


When you reuse an artifact, a trace relationship is established between the new artifact and the original artifact.

A **reuse** icon  appears in the *Indicators* column, which you can click to open the relationship in the utility panel (*Relationships* tab, *Reuse* group).

Note: If the reuse icon is grayed out, you do not have the permissions to view the original artifact.


Note: If the **Override read-only settings** check box is available in the *Reuse* dialog, you have the ability to select the setting, which allows you to ignore any read-only configuration. As a result, you will be able to edit any of the reused artifact properties as well as any additional settings, such as relationships, attachments and document references.

Reconciling reused artifacts

The **suspect** icon  appears when an artifact in a reuse relationship is out of sync. Blueprint gives you a variety of options to reconcile a reused artifact, including:

- **Detailed** option
You can overwrite individual properties from either artifact in the reuse relationship.
- **Overwrite** options
You can completely overwrite one of the artifacts in the reuse relationship.
- **Clear Suspect**
You can remove the suspect flag although technically the artifact(s) will remain out-of-sync.

To reconcile a reused artifact:

1. Click the **suspect** icon  on the artifact you want to reconcile (*Indicators* column).
The reuse relationship appears in the *Relationships* tab.
2. Right-click the reuse relationship you want to reconcile.
3. Select *Reconcile* and then click a reconciliation option.
If you click the **Detailed** option, a dialog appears and you can select which properties to overwrite.
If you click one of the overwrite options, a confirmation dialog appears. Click **OK**.

You have successfully reconciled the reuse relationship.

About spell check


Blueprint provides a spell check so your requirements can be communicated more clearly. Within rich text fields, misspellings are automatically detected and appear underlined in red. The built-in spell check recommends spellings, letting you make the final decision about the right word for your requirement.

The spell check also lets you add a term to the Dictionary when a word is spelled correctly but the word does not exist in the Blueprint Dictionary yet.

Blueprint allows you to ignore the detection of a misspelling at your convenience.

Recommended spellings


When Blueprint detects a misspelling in a rich text field, you can right-click the misspelling to view recommended spellings. You can click the proper word, which replaces the misspelling.



Ignore all

When you want Blueprint to ignore the misspelling of a word in a rich text field, you can right-click the word and select **Ignore All**.


As a result, Blueprint ignores all instances of the word in all of your projects.



Adding a term to the Dictionary

Note: After you add a term to the Dictionary, you cannot remove the term from the Dictionary.

When you spell a term correctly and the word is mistaken for a misspelling, you can add the term to the Dictionary.



When you add a word to the Dictionary, the spelling of the word is accepted in all users's projects. The Dictionary is a database of accepted terms that is shared by all users.

Example





Sam adds the term *BankingCompanyTM* to the Dictionary.

Afterwards, Jesse types the term *BankingCompanyTM* in a rich text field within his artifact. The typed word does not appear underlined in red because the term *BankingCompanyTM* now exists in the Blueprint Dictionary.

The difference between Ignore All and Add to Dictionary

By using either feature (**Ignore all** or **Add to Dictionary**), you can make the detection of a misspelling (red underlining) disappear.

However, performing the above operations (**Ignore All** and **Add to Dictionary**) affects users differently, as this table demonstrates:

Operation applies to:	Ignore All	Add to Dictionary	Explanation
All projects			When you use the Ignore All or Add to Dictionary functionality, all projects are affected whether they are open or closed.
All users			Performing Ignore All does not affect all users whereas performing Add to Dictionary affects all users.

The difference between spell check and the glossary

Spell check detects the incorrect spelling of words.

A glossary is an artifact that contains compiled terms and definitions, often for shared use among project members only.

Adding a term to the Dictionary

When you type a word that is mistaken for a misspelling, you can add the term to the Dictionary.

To add a term to the Dictionary:

Note: After you add a term to the Dictionary, you cannot remove the term from the Dictionary.


1. Type your word and then right-click your word.
The **Add to Dictionary** command appears.
2. Click **Add to Dictionary**.
Your word has been added to the Dictionary.

The spelling checker now accepts the spelling of the word in all users's artifacts and projects.

Disabling the spell checker

The spell checker detects misspellings within rich text fields. Misspellings appear in red and underlined. You have the option of disabling the spell check.

To disable the spell checker:


1. Click the *menu* button on the ribbon.

2. Click the **Profile Options** button on the *application menu*.
The Profile Options dialog box appears.
3. Select the **Disable Spell Check** check box.
4. Click **OK**.

Now the spell checker does not detect misspellings, nor suggest recommended spellings.

Enabling the spell checker

The spell checker detects misspellings within rich text fields. Misspellings appear in red and underlined.

To enable the spell checker:

1. Click the *menu* button on the ribbon.

2. Click the **Profile Options** button on the *application menu*.
The Profile Options dialog box appears.
3. Deselect the **Disable Spell Check** check box.


If you select the **Disable Spell Check** check box, the spell check no longer detects misspellings in rich text fields.

4. Click **OK**.


The spell checker now detects misspellings in rich text fields and suggests recommended spellings.

About locks

Overview

The lock mechanism ensures that two people do not edit an artifact at the same time. The *lock* indicator  appears in the artifact list beside all artifacts that you are editing, regardless of whether your changes are saved or not.

Note: The lock will only appear if the artifact was previously published.

When you start editing an artifact and the lock indicator appears, other users cannot modify the artifact, unless *Steal Lock* privileges are possessed. When an artifact is locked, other users only see the read-only indicator  along with the last published version of the artifact. Private changes are not made publicly visible to other users and the lock is not released until you publish your changes.


When any user possesses the lock and is editing an artifact, any other user with **Steal Lock** privileges has the ability to discard the previous user's changes. For more information on stealing a lock, see [Stealing a lock](#).

Stealing a lock

Note: **Steal Lock** is an action that is only available to users who are assigned to a role with the *Steal Lock* privilege.

The *Steal Lock* feature is useful in situations when a person needs to edit an artifact but it is locked by another user. Ideally, you would contact the user who holds the lock and ask them to either publish or discard their changes. However, if the user is unreachable, it may be necessary to steal the lock.

Stealing a lock involves selecting or opening an artifact that is being edited by another user and discarding their changes by clicking the **Steal Lock** button.




Stealing a lock effectively:

- Deletes the other user's private draft
- Releases the lock so other users can edit the artifact.

Warning: When the **Steal Lock** feature is used, all changes made by the current lock holder are lost! You may want to contact the individual before discarding their changes to prevent the loss of work.

If you need to edit an artifact that is locked, you can verify who has locked it by opening the artifact. A header appears with the name of the user that is currently editing the artifact.



To steal a lock:

1. Open the locked artifact.

A header appears with the name of the user that is currently editing the artifact.

Warning: When the **Steal Lock** feature is used, all changes made by the current lock holder are lost! You may want to contact the individual before discarding their changes to prevent the loss of work.

2. Click the **Steal Lock** button (*Home* tab, *Artifacts* group).

The *Steal Lock* dialog appears.


3. To steal the lock and discard the other user's unpublished changes, click **Yes**.

The other user's changes have been discarded. You now have control to edit and publish changes to the artifact.

View management and saved views

A view refers to the artifact list settings that control what and how information is displayed in the artifact list.

Blueprint remembers which view you selected for individual folders. You can see which view you are using by looking at the ribbon (*View* tab, *Artifact List* group):



The **System** view automatically saves your artifact list view settings. At any time, you can select the **System** view to restore your last used settings. The **System** view, therefore, can be different for each user because it saves the last used settings. This view cannot be reset. The **System** view is sufficient for many users, while others may want to take advantage of [Saved Views](#).

Artifact list view settings and scope

Views consist of the following artifact list settings:

- **Show/Hide Columns**
You can configure which columns of data are displayed in the artifact list by clicking **Column Options** (*View* tab, *Artifact List* group).
- **Column Order**
You can configure the order of columns in the artifact list by clicking **Column Options** (*View* tab, *Artifact List* group) or by dragging and dropping columns in the artifact list.
- **Column Sort Order**
To adjust the column sort order, click a column header in the artifact list.
- **Column Filters**
To adjust the filter settings, click the filter ▼ button in the artifact list column headers.
After applying a column filter, the filter icon changes to yellow ▼. The yellow filter icon is a visual reminder that the filter is applied.
- **Column Width**
To adjust the column width, drag and drop the edge of a column in the artifact list.

Saved Views

Saved views allow you to save your artifact list view settings so you can easily restore those settings at any time. For example, you may want one view that only displays basic artifact information, and another view that displays detailed information such as custom properties.

Note: Blueprint allows you to create and customize views on a project basis. When you create a view, it only appears in the project where you originally created the view.

You can make your views private, or you can share your views so other users can take advantage of your view settings. When you create a shared view, you can control whether or not other users have the ability to modify or delete the shared view.

When you modify artifact list settings to values that differ from the view that is currently activated, an asterisk (*) is displayed beside the view name. You can click the **Reset** button at any time to revert back to the saved view settings. If you are using a *Private* or *Shared (Allow Modifications)* view, you can click the **Save View** button to [modify the view that is currently selected](#) by overwriting the existing view settings. Alternatively, you can use the **Save View As** button to [create a new view](#) using the current artifact list settings.

Tip: Be careful when you are using shared views because shared views can be changed by all users and/or the creator of the view, depending on the type of shared views. If you depend on a shared view to perform tasks, you may want to consider [duplicating the view](#) and saving it as a private view so that it cannot be modified without your knowledge.

Saved View Types

There are three types of views:

- **Private**

When you create a private view, you are the only user who can use and modify the view.


- **Shared (Read-Only)**

When you create a Read-Only Shared view, all users can use the view. However, you are the only person who can modify the view.

- **Shared (Allow Modifications)**

When you create a Shared (Allow Modifications) view, all users can view and modify the view.

Tip: You can zoom in and out of the *main content area* by using the **Zoom** controls at the bottom right of the window.



Alternatively, you can use your browser's zoom settings to enlarge or minimize all contents of the Blueprint window.

Selecting a view

When you select a view, your artifact list settings are automatically changed with the settings that are stored in the selected view. Read more about the [scope of views](#) to learn about the settings you can save and restore using views.

Saved views allow you to save your artifact list view settings so you can easily restore those settings at any time. For example, you may want one view that only displays basic artifact information, and another view that displays detailed information such as custom properties.

Tip: Be careful when you are using shared views because shared views can be changed by all users and/or the creator of the view, depending on the type of shared views. If you depend on a shared view to perform tasks, you may want to consider [duplicating the view](#) and saving it as a private view so that it cannot be modified without your knowledge.

When you modify artifact list settings to values that differ from the view that is currently activated, an asterisk (*) is displayed beside the view name. You can click the **Reset** button at any time to revert back to the saved view settings. If you are using a *Private* or *Shared (Allow Modifications)* view, you can click the **Save View** button to [modify the view that is currently selected](#) by overwriting the existing view settings. Alternatively, you can use the **Save View As** button to [create a new view](#) using the current artifact list settings.

To select a different view:

1. Click the **Current View** option on the ribbon (*View* tab, *Artifact List* group) and select the view you want to select.

After you select a view, your artifact list is immediately updated with the view settings.

Adding a new view


Saved views allow you to save your artifact list view settings so you can easily restore those settings at any time. For example, you may want one view that only displays basic artifact information, and another view that displays detailed information such as custom properties.

You can add as many views as you need. You can also share views so that other users can take advantage of the view you created.

To add a new view:

1. Set your artifact list options the way you want them. Read more about the [artifact list settings that are saved and restored using views](#).
2. Click the **Save View As** button on the ribbon (*View* tab, *Artifact List*).

The save dialog appears:



3. Specify a name for the new view.
4. Specify a **View Type**.

The following view types are available:

■ Private

When you create a private view, you are the only user who can use and modify the view.

■ Shared (Read-Only)

When you create a Read-Only Shared view, all users can use the view. However, you are the only person who can modify the view.

■ Shared (Allow Modifications)

When you create a Shared (Allow Modifications) view, all users can view and modify the view.


5. Click **OK**.

The view is automatically selected after you add the view. You can easily [select a different view](#) at any time.

Duplicating a view

Duplicating a view allows you to create a new view using the artifact list settings that were saved in an existing view.

To duplicate a view:

1. Click the **Manage Views** button (*Views tab, Artifact List group*).
2. Click the view that you want to duplicate.
3. Click the *duplicate*  button.
The duplicate view appears in the list with **(2)** appended to the end of the name.
4. Double-click the name of the duplicated view to modify the name. You can also double-click the view type if you want to change the type.
5. Click **OK**.

You can click Cancel instead of OK if you want to discard your changes.

Modifying a view

After you have created a view, you can modify the view settings, the name of the view, and the type of view.

You can modify the following views:

- any of your own *private* views
- any *Shared (Read-Only)* views that you created
- any *Shared (Allow Modifications)* views that you or other users created

To modify the view settings:

1. Click the **Current View** option on the ribbon (*View tab, Artifact List group*) and select the view you want to modify.
2. Change the [artifact list settings](#).
A asterisk (*) appears beside the view name to indicate that there are changes. You can click the **Reset View** button at any time to discard changes to a view.
3. Click the **Save View** button on the ribbon (*View tab, Artifact List group*).

To modify the name or type of a view:

1. Click the **Manage Views** button (*View tab, Artifact List group*).
2. Double-click the view name or view type that you want to change and then make your modifications.
3. Click **OK**.

You can click **Cancel** instead of **OK** if you want to discard your changes.

Deleting a view

You may want to delete views if you no longer need the view or if you find a duplicate, for example.


Note: You cannot delete the **System** view.

You can delete the following views:

- any of your own *private* views
- any *Shared (Read-Only)* views that you created
- any *Shared (Allow Modifications)* views that you or other users created

Warning: When you delete a Shared view, other users can no longer access the view. If you delete a view that another user is using, the **System** view is automatically selected for that user. You cannot delete the System view at any time.

To delete a view:


1. Click the **Manage Views** button (*Views tab, Artifact List group*).
2. Click the view that you want to delete.
3. Click the *delete*  button.
4. Click **OK**. You can click Cancel instead of OK if you want to discard your changes.

After you delete a view, the view no longer appears as an option in the **Current View** selection menu.

Expanding or collapsing all artifacts in the artifact list

Blueprint provides you with the ability to quickly expand all artifacts in the artifact list as well as to collapse all artifacts.

The **Expand All** and **Collapse All** buttons are accessible in the *View tab (Artifact List group)*:



To expand all artifacts:

1. Right-click any column header in the main content area.

Name	Description	Artifact Type	Indicators
MODEL INFORMATION			
Use Case Diagram (BP Air)	281 Name: BP Air	Textual Requirement	
Requirements	3419	Use Case Diagram	
Glossaries	PF5803302	Folder	
Actors	PF5803304	Folder	
Business Processes	PF5803295	Folder	
Use Cases	PF5803298	Folder	
UI Mockups	PF5803291	Folder	

The context menu appears.

2. Click the **Expand All** button.

Your artifacts and folders expand, showing all child artifacts.

To collapse all artifacts:

1. Right-click any column header in the main content area.


Name	Description	Artifact Type	Indicators
MODEL INFORMATION			
Use Case Diagram (BP Air)	281 Name: BP Air	Textual Requirement	
Requirements	3419	Use Case Diagram	
Glossaries	87	Folder	
Actors	PF5803302	Folder	
Business Processes	PF5803304	Folder	
Use Cases	PF5803295	Folder	
UI Mockups	PF5803298	Folder	
	PF5803291	Folder	

The context menu appears.

2. Click the **Collapse All** button.

Your artifacts and folders collapse, hiding all child artifacts.

Tip: You can zoom in and out of the *main content area* by using the **Zoom** controls at the bottom right of the window.




Alternatively, you can use your browser's zoom settings to enlarge or minimize all contents of the Blueprint window.

About Global Search

Blueprint allows you to perform searches in your current project, or across multiple open projects.

The search field located above the ribbon in the upper right of the application allows you to search using a single piece of text or a text string. Using a wildcard [*] at the end of your term can increase your search results in any textual property for any Artifact & Sub-Artifact:[±]




[±] Sub-Artifact searches are restricted to Name, Label, and Description fields.

The Advanced Search follows similar rules to the Global Search, with the added functionality of the ability to search any user (excluding groups and imported users) property, and across all projects in the instance (closed or open). Advanced Search drills down into the Name, Label, and Description fields when searching through sub-artifacts to return even more results. It should be noted that each additional **Property** in the search is treated as an **AND** condition.

Example

Stakeholders have requested that the “CSR” position title be modified from “Customer **Service** Representative” to “Customer **Support** Representative”. You complete an Advanced Search query to retrieve all Artifacts that contain the Name “CSR”, as shown below:



Property	Operator	Value
Name	Contains	CSR

☒ Include sub-artifacts

Search Cancel

Note: We highly recommend that project administrators use custom properties to organize project and artifact data. In addition to enhancing project and content structure, custom properties can be searched and filtered efficiently.


To refine your search, Blueprint allows you to use operators as well as specify values.

To narrow your search results, you can restrict your search to particular project(s). After you select one or more projects, the properties you can search become available.

Using an operator in your search

To help refine your search, Blueprint provides a number of operators in the drop-down menu. Operators define the relationship between a property and a specified value.

Note: In the example below, the user is searching for items that were completed on a specified date (07/07/2015).



Property	Operator	Value
Created On	Equal	7/7/2015

☐ Include sub-artifacts

Search Cancel

Depending on the property chosen, you may be able to use any of the following operators:

- **Equal**
Returns items with the specified value.
- **Not Equal**
Returns items that do not have the specified value.
- **Empty**
Returns items that do not have data in the specified property.
- **Is Not Empty**
Only returns items that have data in the specified property.
- **Greater Than**
Returns items that have occurred after the specified date or are greater than the specified number.
- **Less Than**
Returns items that have occurred before the specified date or are less than the specified number.

Note: Only the operators that are relevant to the property chosen will be available in the drop down list. For example, a Created By property will not have operators related to date (on, or before).

Search results

After you submit search criteria, search results open in a new tab. You can filter and sort search results like you would sort and filter artifacts in an artifact list.

PR278146: Wyngs... Search Result(s): ...										
<div> <div>Projects To Search: All Projects</div> <div>Search Result(s): 175 Artifact(s) Found</div> <div>Query: Created On = 7/7/2015</div> </div>										
Project Name	Name	ID	Artifact Type	Artifact Path	Created By	Created On	Last Edited By	Last Edited On	Project Path	
Internal Enhancement Requests	Allow for a true boole	ER278143	Enhancement Request	Internal Enhancement Re	Matthew Lui	7/7/2015 11:02 AM	Handika Handoko	7/13/2015 4:36 PM	/Blueprint/Product Manag	
Wyngs Air - Reservation System	Business	PF278147	Folder	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Application	PF278148	Folder	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Document Output	PF278149	Folder	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Wyngs Air.docx	DOC278150	Document	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Login	UC278151	Use Case	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Online chat	BUS-RQ278152	Business Requirement (Nonstandard)	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Manage Account online	BUS-RQ278153	Business Requirement (Nonstandard)	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Browser Support	QS-RQ278154	Quality of Service Requirement	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Business Rules	PF278155	Folder	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Points for Platinum m	BUS-RL278156	Business Rule	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	
Wyngs Air - Reservation System	Book a Flight	UC278157	Use Case	Wyngs Air - Reservation S	Aman Bhalla	7/7/2015 1:23 PM	Aman Bhalla	7/7/2015 1:23 PM	/Blueprint/Sample	

Each search result shows up on a new line with the following details:

- **Project Name**
- **Name**
- **ID**
- **Artifact Type**
- **Artifact Path**
- **Created By**
- **Created On**
- **Last Edited By**
- **Last Edited On**
- **Project Path**

The default search results are sorted by last modified. You can edit your search by clicking the query link at the top of the search results, or change the default sort in web.config. For more information on how to edit web.config consult your support team.

The maximum number of search results that can appear is **1000**, which is a system configurable value.

Tip: You can export your search results to a Microsoft Excel file by clicking the **Artifact List View** button on the ribbon (*Import/Export* tab, *Export* group). You must save it as a **.xls** or **.html** file in order to open the file later.

Searching for artifacts

Searching for artifacts and sub-artifacts provides a quick and easy way to find the artifact that you want to view or modify. If you know where the artifact is located, you may prefer to browse to find it. Read more about [Browsing artifacts](#).


If you only remember part of the name, can't recall the location, or only know a piece of information in the artifact's textual properties it may be more efficient to use one of the search features.

To complete a Global Search:

1. In the upper right of the application, enter your text into the **Search** box.

A search input box with the placeholder text "Search". To the right of the text input is a magnifying glass icon and a small downward-pointing arrow.

2. Select one of the Projects to Search options.


A dropdown menu titled "Advanced Search". It contains two radio button options: "Current Project" (which is selected) and "All Open Projects".

3. Click the Search icon .

A new tab appears with search results.

To complete an Advanced Search:

1. In the upper right of the application, click the **Advanced Search** link.

A rectangular button with the text "Advanced Search" in blue.

2. The Advanced Search window appears. Select a property to search.

Property	Operator	Value
+ - Name	Contains	CSR
+ Add another property		

☒ Include sub-artifacts

Search Cancel

Note: To include sub-artifacts in your advanced search, you must check off the **Include sub-artifacts** box in the Search window.

3. Choose an operator from the drop down.
When search criteria needs to be specified, the **Value** field appears.
4. To add an additional property to search, click .
Each additional property in the search is treated as an **AND** condition.
5. Click **Search**.

The search results are displayed in an expanded tree view, helping you find the one you are looking for, even if there are many similar results.

After you have located the artifact that you want, you can:


- [open the artifact](#)
- [share the artifact](#)
- [create a trace to/from the artifact](#)

About the utility panel


Overview

The utility panel is located on the right side of the Blueprint user interface. The utility panel allows you to view detailed information about an artifact such as properties, comments, files, traces, and history. You can also use the utility panel to access review information.




The utility panel looks like this:




A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:




Resizing and expanding/collapsing the utility panel








You can resize the utility panel by pointing to the vertical border. When the double arrow  cursor appears, click and drag the panel border to the left and right to increase or reduce the width of the panel. You can also expand and collapse the utility panel using the expand  and collapse  buttons.

Tip: To make more space available to view your artifact(s), you can collapse both the utility panel and the explorer panel by clicking the full screen button  (the lower rightmost corner of the window).

Understanding the utility panel tabs

There are 8 tabs located in the utility panel. Each tab provides you with the ability to view different information about the artifact.

Icon	Tab Name	Description
	Properties	The <i>properties</i> tab allows you to view and change artifact properties.

Icon	Tab Name	Description
	Comments	The <i>Discussions</i> tab allows you to view comments, create new comments, reply to existing comments, and change the status of discussions.
	Files	The <i>files</i> tab allows you to view, add, and delete artifact file attachments and document references.
	Relationships	The <i>Relationships</i> tab in the utility panel allows you to view and add artifact traces, effectively establishing relationships with other artifacts.
	Outline	The <i>outline</i> tab provides you with an outline view of the artifact. The outline view of an artifact shows the parent-child relationships of a diagram. The outline view presents the artifacts and sub-artifacts in a tree-view style, making it quick and easy to navigate diagrams.
	Search	The <i>browse</i> tab allows you to browse and search for all types of artifacts.
	History	The <i>history</i> tab allows you to view previous versions of the artifact and compare changes between them.
	Reviews	The <i>reviews</i> tab provides you with a list of all reviews that contain the artifact.

About artifact properties

An *artifact property* refers to the descriptive data that is associated with an artifact or sub-artifact. All artifacts and sub-artifacts have default system properties. These default system properties vary depending on the type of artifact or sub-artifact. Artifacts can also have standard properties (configured by instance administrators) and/or custom properties (configured by project administrators). Sub-artifacts can have custom properties as well, which are configured by project administrators.

The *properties* tab allows you to view every property that is associated with an artifact or sub-artifact. The *properties* tab on the utility panel looks like this:

» Utility Panel

UC4668432: Online Banking

▲ Properties

Name	Online Banking
Id	UC4668432
Type	Use Case
UseCase Level	1
Priority	High
Effort in Days	0
Stability	0

▲ Author History

Created By	Christina McNish
Last Edited By	Christina McNish
Created On	21/02/2013 9:19 AM
Last Edited On	21/02/2013 9:19 AM

▲ Details

Description

Top Level use case in the Online Banking system.

Understanding the properties tab in the utility panel

A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:

» Utility Panel

GD4668410: Online Banking System Interfaces

▲ Properties

Name	Online Banking System...
Id	GD4668410
Type	Generic Diagram
Width	1308
Height	768

The *property* tab displays all associated properties, including default system properties, any standard properties configured by the instance administrator and any custom properties configured by the project administrator. You can expand and collapse the headings (example: *Properties*, *Description*) to show or hide the information.

Viewing and changing artifact and sub-artifact properties

To view the properties of an artifact, simply open the artifact and click the *properties* tab in the utility panel. If you want to view the properties of a sub-artifact, you must open the artifact that contains the sub-artifact, and then select the sub-artifact. For example, if you want to view the properties of a shape in a diagram, you must open the diagram and click the shape (sub-artifact) to view the properties.


Changing the value of a property is as simple as changing the information that appears in the *properties* tab. Some properties, such as the ID, cannot be modified.

Note: You must publish the artifact before your changes are viewable by other users.

Performing a bulk update

The bulk update feature allows you to update your artifacts more efficiently. When you have an update you need to apply across multiple artifacts, bulk update lets you apply the change with one simplified action. You can bulk update up to 5000 artifacts.

In the main content area, simply select the artifacts that you want to update and then click the **Bulk Update** button:



Name	ID	Description
Reserve Online	TR_RU4405714	BP Air needs to allow customers to reserve online.
Edit Reservations	TR_RU4405715	BP Air needs to allow customers to edit their reservations online.
Cancel Reservations	TR_RU4405716	BP Air needs to allow customers to cancel their reservations online.

You can bulk update any of your artifacts's properties or artifact types. Read-only artifacts are the only artifacts that cannot be updated in bulk.

To perform a bulk update:


Important: If you undo a bulk update because the bulk update results do not meet your expectations, the undo is *not* automatically published.

Tip: Before you do a bulk update, we recommend publishing or discarding any desired changes. If the bulk update does not meet your expectations, you can discard all changes without losing work.

1. In the main content area, select the artifact(s) and/or folder(s) you want to change and then click **Bulk Update** (*Home* tab).
The *Bulk Update* dialog box appears.
2. To update a property or artifact type, select it from the **Select property to bulk update** menu and then click the **Add** button.


The property or artifact type appears below the menu.

To remove a property or artifact type, click the red **X** next to the property field.



Tip: By selecting the **Apply changes to all children of the selected artifact(s)** check box, you can also update the child artifacts of the selected parent artifacts.

3. To update another property or artifact type, perform the previous step again.
4. Make your changes in the fields that appears next to your properties or artifact type.



Note: When the blue information icon appears next to a property or artifact type you want to update, the property is not shared by all of the artifacts you selected. The update will not apply to all of your artifacts.

5. When you have made all of your changes, click **Update**.
If your update succeeded, your artifacts appear with lock icons in the main content area.
6. To apply the bulk update to your artifacts, click the **Save All** button or **Publish All**.

Artifact outline


The outline view of an artifact shows the parent-child relationships of a diagram. The outline view presents the artifacts and sub-artifacts in a tree-view style, making it quick and easy to navigate diagrams. You can click any sub-artifact in the outline view, and the sub-artifact is automatically selected in the artifact editor.

Example


Deb, a business analyst, wants to make some modifications to a large and complex business process diagram. She has tried using the zoom feature to view the entire diagram in the main content area, but now the text is too small to read. She has also tried scrolling up and down the diagram, but she keeps losing her place.

Deb finds the artifact outline in the utility panel and ends up saving herself some time. She can easily navigate the diagram using the tree view of the sub-artifacts. Deb still uses the graphical view of the diagram, but she usually uses the artifact outline to locate a specific area.

The artifact outline is available on the *outline* tab in the utility panel. The *outline* tab looks like this:



A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:



Applicability

Note: The outline view is not available for all artifact types.

The outline view is available for the following artifacts:


- Use Cases
- Business Process Diagrams
- UI Mockups
- Storyboards
- Generic Diagrams
- Domain Diagrams

You must open an artifact before you can use the outline view. In other words, the outline view is not available if you simply select an artifact in the artifact list. If the outline view is not applicable for any reason, the following message is displayed on the *outline* tab: **There are no items to show. This function is not applicable for the selected item.**

Displaying the outline view of an artifact

The outline view of an artifact shows the parent-child relationships of a diagram. The outline view presents the artifacts and sub-artifacts in a tree-view style, making it quick and easy to navigate diagrams.

To display the outline view of an artifact:

1. Open an artifact that supports the outline view.
Click the artifact ID link of the artifact you want to open.
Blueprint offers the outline view for the diagram artifacts. View the [full list of supported artifact types](#).
2. Open the *outline* tab in the utility panel.
 1. Click the *outline* tab  icon.


You can also point to the tab icon to view the name of the tab.

You can expand and collapse the sub-artifacts in the outline view in order to navigate the hierarchy. For example, all Lanes in a business process diagram can be expanded to view the sub-artifacts contained within the lane.

Expanding or collapsing all artifacts in the artifact list


Blueprint provides you with the ability to quickly expand all artifacts in the artifact list as well as to collapse all artifacts.

The **Expand All** and **Collapse All** buttons are accessible in the *View* tab (*Artifact List* group):



To expand all artifacts:

1. Right-click any column header in the main content area.




The context menu appears.

2. Click the **Expand All** button.

Your artifacts and folders expand, showing all child artifacts.

To collapse all artifacts:

1. Right-click any column header in the main content area.




The context menu appears.

2. Click the **Collapse All** button.

Your artifacts and folders collapse, hiding all child artifacts.

Tip: You can zoom in and out of the *main content area* by using the **Zoom** controls at the bottom right of the window.




Alternatively, you can use your browser's zoom settings to enlarge or minimize all contents of the Blueprint window.

Artifact searching and browsing

Searching and browsing provides a fast and efficient way to locate artifacts in Blueprint. If you know where the artifact is located, you may prefer to browse to find the artifact. If you remember part of the artifact name, can't recall the location of the artifact, or need to view a list of artifacts that meet a certain criteria, take advantage of the Global Search feature.


You can also [search for artifacts and sub-artifacts](#) within the selected project. To help you find artifacts more easily, Blueprint allows you to restrict your search to a particular type of artifact, or even search for an artifact by its ID (only possible in Utility Panel Search).

The *browse*  tab in the utility panel allows you to browse artifacts and sub-artifacts within any single project, provided you have sufficient access to the project and the artifacts.

The *browse* tab in the utility panel looks like this:



A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:



Browsing artifacts

You can browse for both artifacts and sub-artifacts within any project, provided you have sufficient access to the project. By default, the current project is selected. If you cannot find the artifact you are looking for, you may want to consider [searching](#) instead.

To browse artifacts using the *Browse* tab in the utility panel:

1. Select the project that you want to browse.

To select a different project, simply click the project drop-down that is located under the search field. Then, expand the folders until you locate the project you want. Click the project to display the contents in the utility panel.

2. Expand the folders and artifacts to locate the artifact you are trying to find.

Simply click the expand buttons (or double-click the artifacts) to display the contents of each artifact.

Tip: To see the location of an artifact or folder in the artifact list, right-click an artifact in the *Browse* tab and then click **Show Location**. The corresponding artifact or folder is selected in the artifact list.

After you have located the artifact that you want, you can:

- [open the artifact](#)
- [share the artifact](#)
- [create a trace to/from the artifact](#)

Opening artifacts from the utility panel browse tab

While you are browsing or searching for artifacts, you may want to open an artifact from the *browse* tab in the utility panel.

To open an artifact from the utility panel browse tab:

1. Open the *browse* tab in the utility panel.

Click the *browse* 🔍 tab.

You can also point to the tab icon to view the name of the tab.

2. Right-click the artifact that you want to open.

The context menu appears.

3. Click Open.

The artifact opens in a new tab in the main content area.

File attachments and document references

File attachments and document references allow you to associate content in a file (or document) with an artifact or sub-artifact. A *document reference* is an existing document artifact that you can associate with one or more artifacts. A *file attachment* is a file that you upload and associate with a single artifact.

Example

Jeff, a business analyst, is working on a business process and wants to add a photo of a rough diagram that was drafted during a recent meeting. In this case, Jeff uploads the photo as a file attachment because he does not intend to reference the photo from any other artifacts.


Example

Joe, from the legal department, recently created a new document artifact and uploaded a terms and conditions document. The terms and conditions must be accepted by users prior to creating a new account in the system.


Sally, a business analyst, has been notified by the legal department that users must accept the same terms and conditions prior to using the system to make a purchase. In this case, Sally opens the Purchase use case, and adds the terms and conditions as a document reference. Now, there are multiple references to the same document artifact.

Document artifacts are different than file attachments. Document artifacts can be referenced from multiple artifacts by adding it as a document reference to other artifacts in the utility panel *files* tab. File attachments are also added in the *files* tab of the utility panel and are associated with a single artifact.

The *files* tab allows you to view, add, and delete artifact file attachments and document references. The *files* tab in the utility panel looks like this:



A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:



Determining whether or not an artifact contains file attachments or document references

When an artifact contains file attachments or document references, the *files* 📎 indicator is displayed in the *Icons* column in the artifact list. Click the **Column Options** button on the ribbon *view* tab to enable the display of this column.

You can also view the *file* indicator in the upper right corner of each sub-artifact (example: shape) that contains file attachments or document references.


Adding a file attachment to an artifact

A *file attachment* is a file that you upload and associate with a single artifact. Blueprint allows you to add multiple file attachments to an artifact.

Tip: If you plan to upload the file to multiple artifacts, you may want to create a [document artifact](#) instead. If you create a document artifact, you can then [add a document reference](#) to multiple artifacts.

Note: Blueprint enforces a maximum file size for file attachments. The maximum file size is configurable by your project administrators.

To add a file attachment to an artifact:

1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *files* tab in the utility panel.
Click the *files* tab  icon.
3. Click **New** and select **Add Attachment**.
4. Select the file that you want to attach.
Search or browse to locate the file that you want to upload and attach to the artifact.
5. Click **Open**.


Adding a document reference to an artifact

A *document reference* is an existing document artifact that you can associate with one or more artifacts. Blueprint allows you to add multiple document references to an artifact.

Before you can add a document reference to an artifact, the document artifact must already exist. If the document has not already been uploaded to a document artifact, you may want to create a document artifact. Read more about [Adding a document artifact](#).

Tip: If the document is only applicable to a single artifact, you may want to add the document as a file attachment instead. See [Adding a file attachment to an artifact](#) and [File attachments and document references](#) for more information.


To add a document reference to an artifact:

1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *files* tab in the utility panel.
Click the *files* tab  icon.
3. Click **New** and select **Add Document Reference**.
4. Select the document artifact that you want to reference.
Search or browse to locate the document artifact that you want to reference.
5. Click **OK**.

Opening a file attachment or document reference

You can open file attachments and document references directly from the files tab in the utility panel. Blueprint also provides you with an easy way to open the document artifact for any existing document references.

To open a file attachment or document reference:


1. Open the artifact that contains the file attachment or document reference that you want to view.
Click the artifact ID link of the artifact you want to open.
2. Open the *files* tab in the utility panel.
Click the *files* tab  icon.
3. Right-click the file attachment or document reference that you want to view.
The context menu appears.
4. Click **Open**.
When you open a file attachment or document reference, the file is automatically downloaded to your computer in a temporary directory. Your computer then decides which application is most appropriate for opening the file.

Tip: You can also open the document reference artifact by selecting **Open In Application**.

Deleting a file attachment or document reference

When you delete a file attachment, the file is permanently removed from the system and is not available in historical versions of the artifact. However, when you delete a document reference, the reference is removed but the document artifact remains available in the system.

To delete a file attachment or document reference:


1. Open the artifact that contains the file attachment or document reference.
Click the artifact ID link of the artifact you want to open.
2. Open the *files* tab in the utility panel.
Click the *files* tab  icon.
3. Right-click the file attachment or document reference that you want to delete.
The context menu appears.
4. Click **Delete**.

Warning: There is no delete confirmation dialog. The file attachment or document reference is immediately removed. However, the deletion is not permanent until after you publish your changes.

Note: You must publish the artifact before your changes are viewable by other users.

About rich text formatting

Blueprint provides you with the ability to create textual content using rich text formatting. In other words, you can perform many of the operations that you can perform using a word processing application. The rich text formatting features are available on the ribbon *Home* tab:




Here's a list of the rich text formatting features offered by Blueprint:

- Change font type, color, and size
- Make the font bold, italic, underline, subscript, superscript, strikethrough
- Apply highlighting to font
- Add a hyperlink
- Create a bulleted or numbered list
- Change the paragraph justification

Rich Text Formatting in the Artifact List

Rich text formatting is displayed differently in the artifact list depending on the current mode. Here's an explanation of the different modes and the way rich text formatting is displayed:

- Edit in-place mode
 - all rich text formatting is displayed.



- Non-edit and wrap text disabled:
 - text is displayed as plain text.



- on hover, a tooltip displays a limited amount of rich text. Bullets and lists are not displayed in the tooltip.




- Non-edit and wrap text enabled:
 - displays a limited amount of rich text. For example: Highlighting, bullets and lists are not displayed.




Keyboard shortcuts

Blueprint offers a number of keyboard shortcuts that allow you to perform various operations in Blueprint using your keyboard instead of your mouse. This article outlines keyboard shortcuts for basic operations in Blueprint.


Many of the operations listed in the table below are also accessible as buttons on the **menu** Menu as well as on the *Home* tab (on the ribbon).



Keyboard shortcuts for basic operations

Keyboard Key(s)			Operation	Result / Effect
Internet Explorer	Firefox and Chrome (Windows operating systems only)	Safari (Mac OS)		
	CTRL + O	CTRL + O	Open a project	The <i>Open project</i> dialog appears as well as a list of projects. You can then open a project.
	CTRL + F4	CTRL + F4	Close the current editor tab	Closes the artifact editor tab that is currently open within the main content area. 

Keyboard Key(s)			Operation	Result / Effect
Internet Explorer	Firefox and Chrome (Windows operating systems only)	Safari (Mac OS)		
ESC	ESC	ESC	Exit current editing operation	This shortcut is equivalent to clicking the Cancel button when in edit mode. This shortcut can be used when editing artifact menus or when editing artifact names in the main content area.
CTRL + Z	CTRL + Z	CTRL + Z	Undo the last action	Undoes most authoring actions, except for save, publish and discard operations.
CTRL + Y	CTRL + Y	CTRL + Y	Redo the last action	Redoes the last action that was undone.
CTRL + X	CTRL + X	CTRL + X	Cut	Cuts text, images and most artifacts. For more information about the cut operation's capabilities, see About copying and pasting . For information about cutting and pasting artifacts across projects, see Moving artifacts from one project to another project
CTRL + C	CTRL + C	CTRL + C	Copy	Copies text, images and most artifacts. For more information about copy's capabilities, see About copying and pasting . For information about copying and pasting artifacts across projects, see Moving artifacts from one project to another project
CTRL + V	CTRL + V	CTRL + V	Paste	Pastes text, images and most artifacts. For more information about paste's capabilities, see About copying and pasting . For information about copying and pasting artifacts across projects, see Moving artifacts from one project to another project
	CTRL + B	CTRL + B	Make the selected text bold	Makes the text you selected in the rich text field bold. For more information about rich text formatting, see About rich text formatting .
	CTRL + I	CTRL + I	Italicize the selected text	Italicizes the text you selected in the rich text field. For more information about rich text formatting, see About rich text formatting .
	CTRL + U	CTRL + U	Underline the selected text	Underlines the text you selected in the rich text field. For more information about rich text formatting, see About rich text formatting .


Keyboard Key(s)			Operation	Result / Effect
Internet Explorer	Firefox and Chrome (Windows operating systems only)	Safari (Mac OS)		
CTRL + SPACEBAR	CTRL + N	CTRL + N	Create new artifact	<p>Selecting an artifact and then pressing CTRL + SPACEBAR creates a new sibling actor artifact.</p> <p>Here is an example of a new artifact that is created (<i>New Actor 7</i>) after selecting the <i>Sign In</i> artifact and then pressing CTRL + SPACEBAR:</p> 
F8	F8	F8	<i>New Artifact</i> right-click menu	<p>Selecting an artifact and then pressing F8 makes the <i>Create New Artifact</i> menu appear. You can then click a command within the menu to add a new artifact or edit the existing selected artifact.</p> 
	CTRL + S	CTRL + S	Save the selected artifact(s)	Saves the artifact that is currently open or the artifact(s) you selected in the artifact list.

Keyboard Key(s)			Operation	Result / Effect
Internet Explorer	Firefox and Chrome (Windows operating systems only)	Safari (Mac OS)		
	CTRL + P	CTRL + P	Export the artifact to a PDF for printing	Exports the artifact you selected to a PDF, making it available to print.
F9	CTRL + SHIFT + S	CTRL + SHIFT + S	Save all artifacts	Saves all changes that have been made to any artifact(s) or folder(s).
DEL	DEL	DEL	Delete	Deletes any selected artifact(s), text or content.
	F5	F5	Refresh the selected artifact	Refreshes the currently open artifact or the selected artifact(s) in the artifact list.
	CTRL + F5	CTRL + F5	Refresh all artifacts	Refreshes all artifacts within an open project.
	F3	F3	Open the <i>search</i> dialog	Opens the <i>search</i> dialog. For more information about the search feature, see About Global Search .
	CTRL + G	CTRL + G	Search for an artifact by ID	Opens the <i>Go To</i> dialog. You can quickly open an artifact by entering an artifact ID and pressing ENTER. Note: You can omit the prefix of the artifact ID when using the <i>Go To</i> dialog.
CTRL + SHIFT + W	CTRL + SHIFT + W	CTRL + SHIFT + W	Manage traces	Within an open artifact, pressing CTRL + SHIFT + W makes the <i>Traces</i> dialog appear. You can then create, modify or delete a trace. When selecting an artifact in a list, pressing CTRL + SHIFT + W makes the <i>Traces</i> dialog appear. You can then create, modify or delete a trace.
	F1	F1	Get help using Blueprint	Opens the <i>Blueprint Help</i> web site for the applicable version of the product in a new window. For help with a different version of Blueprint, see the Blueprint Help Resources web site .

Keyboard Key(s)			Operation	Result / Effect
Internet Explorer	Firefox and Chrome (Windows operating systems only)	Safari (Mac OS)		
CTRL + SHIFT + 1	CTRL + SHIFT + 1	CTRL + SHIFT + 1	Open <i>Keyboard Shortcuts</i> pop-up	The <i>Keyboard Shortcuts</i> dialog appears with a list of all of the <i>Home</i> tab shortcuts mentioned in this table for quick reference.

Viewing a list of shortcuts

To view a list of basic shortcuts within Blueprint, press CTRL + SHIFT + 1.



Keyboard Shortcuts		
Action	Firefox and Chrome	Internet Explorer
General		
Open a project.	Ctrl+O	
Close the current editor tab.	Ctrl+F4	
Exit edit in place.	Esc	Esc
Undo the last action.	Ctrl+Z	Ctrl+Z
Redo the last action.	Ctrl+Y	Ctrl+Y
Clipboard		
Cut the selection and put it on the Clipboard.	Ctrl+X	Ctrl+X
Copy the selection and put it on the Clipboard.	Ctrl+C	Ctrl+C
Paste the contents of the Clipboard.	Ctrl+V	Ctrl+V
Font		
Make the selected text bold.	Ctrl+B	
Italicize the selected text.	Ctrl+I	
Underline the selected text.	Ctrl+U	
Actions		
Create a new artifact.	Ctrl+N	Ctrl+Space
Access the New Artifact shortcut menu.	F8	F8
Save the selected artifact(s).	Ctrl+S	
Export the selected artifact to a PDF document for printing.	Ctrl+P	
Save all artifacts.	Ctrl+Shift+S	F9
Delete the selected item(s).	Delete	Delete
Refresh the artifact you are currently viewing, or the artifact(s) selected in the artifact list.	F5	
Refresh all artifacts.	Ctrl+F5	
Artifacts		
Opens the search dialog.	F3	
Open an artifact by ID. The prefix of the ID can be omitted.	Ctrl+G	
Relationships		
Open the Manage Traces dialog to add, modify, or delete trace relationships.	Ctrl+Shift+W	Ctrl+Shift+W
Help		
Get help using Blueprint.	F1	
Open the keyboard shortcuts pop-up.	Ctrl+Shift+1	Ctrl+Shift+1

Keyboard Navigation

Blueprint offers a number of keyboard navigation shortcuts that allow you to perform various operations in Blueprint using your keyboard instead of your mouse.

Choice Drop-Down Keyboard Navigation


Keyboard Key	Edit Mode	Non-Edit Mode
Arrow Keys	<p>If the drop-down panel is open, arrow keys navigate within the drop-down list panel until end is reached.</p> <p>If the drop-down panel is not open, the arrow keys navigate the list without opening the drop-down panel.</p>	Navigates to next cell.
Tab / SHIFT Tab	Navigates to next cell.	Navigates to next cell.
Enter	<p>If valid, the Enter key commits changes and moves focus to the cell below.</p> <p>If not valid, the Enter key flags field with an inline error and moves focus to the cell below.</p>	Navigates to the cell below.
Space Bar	Opens the drop-down panel, allowing you to use the arrow keys to navigate the drop-down.	Places cell in <i>edit in place</i> mode.
Typing	Takes you to the closest match. If a match cannot be found, you can simply type in a new value.	Places cell in <i>edit in place</i> mode.
ESC	Cancels edit mode.	N/A

Multi-Select Keyboard Navigation

Keyboard Key	Edit Mode	Non-Edit Mode	Pop-Up Open
Arrow Keys	Navigates to next cell.	Navigates to next cell.	Navigates between options in the scrollable list.
Tab / SHIFT Tab	Navigates to next cell.	Navigates to next cell.	Navigates the pop-up content (left to right and top to bottom).
Enter	Navigates to the cell below.	Navigates to the cell below.	Accepts the value and closes the pop-up.
Space Bar	<p>Opens the multi-select dialog.</p> <p>After the dialog is closed, the cell is shown in <i>edit in place</i> mode.</p>	Places cell in <i>edit in place</i> mode and displays the multi-select list.	Selects/Deselects options in the scrollable list.
Typing	N/A	N/A	N/A
ESC	N/A	N/A	Cancels edit mode.

Select Users Dialog Keyboard Navigation

The *Select Users* dialog is applicable for custom properties when the *Type* is set to *User*. The *Select Users* dialog looks like this:



Here are some guidelines for navigating the *Select Users* dialog using your keyboard:

Keyboard Key	Edit Mode	Non-Edit Mode	Pop-Up Open
Arrow Keys	Navigates to next cell.	Navigates to next cell.	Navigates between options in the scrollable list.
Tab / SHIFT Tab	Navigates to next cell.	Navigates to next cell.	Navigates pop-up content (left to right and top to bottom).
Enter	Navigates to the cell below.	Navigates to the cell below.	Accepts the value and closes the pop-up.
Space Bar	Opens People Picker Dialog. After the dialog is closed, the cell is shown in edit in place mode.	Places cell in <i>edit in place</i> mode and displays people picker	Selects/Deselects options in the scrollable list .
Typing	N/A	N/A	N/A
ESC	N/A	N/A	Cancels edit mode.

Moving artifacts from one project to another project

All artifact types can be moved between projects in Blueprint with the exception of review artifacts and baseline artifacts.

Data preservation differences between cross-project move and cross-project copy

Moving an artifact has a different effect from copying an artifact.

The following table shows which artifact data is moved and/or copied within a project compared to across projects:

	Move		Copy	
	In-Project	Cross-Project	In-Project	Cross-Project
Trace relationships	Preserved	Preserved	No	No
Attachments	Preserved	Preserved	Preserved	Preserved
IDs	Preserved	Preserved	No*	No*
Comments	Preserved	Preserved	No	No
Custom properties	Preserved	Depends**	Preserved	Depends**
Document references	Preserved	Preserved	No	No
History	Preserved	Preserved	No	No

*For example, when you copy an artifact, the new copy of the artifact has a different ID from the original artifact.

**A custom property is only preserved when the destination project has the same custom property with the same name and type.

When you move an artifact from one project to another project, the moved artifact is automatically saved but it is not automatically published.

Undoing an artifact move

When you cut or copy an artifact from one project to another project, the **Undo** button is unavailable to undo the action (that is, greyed-out).


To undo your artifact move, manually perform one of the following actions:

- Select your artifact, press CTRL+X and then, to paste your artifact into its original folder, press CTRL+V
- Select your artifact and then drag the artifact back to its original folder.


Moving an artifact from one project to another project

To move an artifact by dragging it from one project to another project:

1. In your artifact list, select your artifact's first column (that is, the column to the left of the *Name* column).



2. Drag the artifact to the project you want to move it to in the *Explorer* area.




Your artifact and any of its related information (for example: ID and comments) now exist solely in the project you have moved it into.

To move an artifact by cutting it from one project and pasting it into another project:

1. In your project, select the artifact you want to move and then press CTRL+X to cut the artifact.

A scissor icon appears next to your cut icon.



2. Place focus on the project or folder into which you want to paste the artifact. Press CTRL+V.

The artifact appears in your artifact list with a lock indicator. The artifact move is saved but not published. To publish the move, click the **Publish All** button.


About copying and pasting

Copying and pasting text

In Blueprint, you can copy text from one artifact and paste it in another artifact. You can also copy text from one project and paste it in another project.

Using the **Ctrl+V** keyboard shortcut to paste preserves any rich text formatting that your text has.

When you copy formatted text (bold, italics, and so on) and click the **Paste** button to paste it, you have the option of pasting your text without formatting or keeping the formatting.



Copying and pasting text examples

Example

Lewis, a business analyst, wants to copy **bolded** and **green** text from his UI mockup and paste it in his textual requirement. All he has to do is copy the formatted text onto his Clipboard, select where he wants to insert the text, and use the **Ctrl-V** keyboard shortcut.

Example

Susan, a business analyst, wants to copy information from her UI mockup and paste it in her textual requirement. The information is **bolded** but she wants to paste the text without formatting. All she has to do is copy the text onto her Clipboard, select where she wants to insert the text, click the **Paste** button, and then click **Paste Unformatted Text**.

Pasting shapes

Blueprint shapes can be copied from one Blueprint artifact and pasted into other artifacts of the same type. Blueprint shapes can be pasted in the same project or pasted into other projects.

Pasting Visio shapes

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

You can copy shapes from Microsoft Visio and paste the Visio shapes in Blueprint diagrams. When you copy a shape from Visio and paste it in a Blueprint diagram, your Visio shape is inserted as an image. When you copy multiple Visio shapes and paste them in a Blueprint diagram, your Visio shapes are inserted as an image.

Shapes can be copied from Microsoft Visio and pasted into the following artifact types:

- UI mockups
- Business process diagrams
- Domain diagrams
- Generic diagrams
- Use case diagrams

Copying artifacts

Caution: When you copy and paste an artifact, trace relationships, IDs and comments are not preserved in the new artifact.

With the exception of review artifacts, baseline artifacts and custom artifact types, all artifact types can be copied from one project and pasted in another project.

Custom artifact types can only be copied and pasted into another project when the destination project has the same custom artifact types.

When an artifact has custom properties, the custom properties can only be copied and pasted into another project when the destination project has the same custom properties.

In Blueprint, you can copy a folder from one project and paste it in another project.

Pasting text in a diagram

To paste text within a diagram shape:

1. Copy the text onto your Clipboard using the **Copy** button or the **Ctrl-V** keyboard shortcut.
2. Open the artifact in Blueprint where you want to paste the text.
Click and drag a text-compatible shape onto the canvas, such as a text area or callout.
3. Click the shape to place focus on it.
4. When the text cursor appears on the shape, click the **Paste** button on the ribbon (*Home* tab, *Clipboard* group) or use the **Ctrl-V** keyboard shortcut.

Tip: To paste the text without formatting, select the **Paste** button on the ribbon (*Home* tab, *Clipboard* group) and then click **Paste unformatted text**.

About pasting images

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

With Blueprint, you can copy and paste images or screen captures from other applications into any Blueprint artifact that supports images, including:

- UI mockups
- Use case diagrams
- Generic diagrams
- Domain diagrams
- Business process diagrams

Maximum image size

You can paste images into Blueprint if the image size on the clipboard is 1900KB or less.

Note: When you copy an image to the clipboard, the image is copied to the clipboard in Bitmap format, which is much larger than a JPG for instance. If the image is too large, you may want to consider using the *Image* shape from the palette to add your shape to the diagram.

Pasting an image into Blueprint

To paste an image into Blueprint:

Note: You can copy and paste images that are up to 1900KB in size.

1. Copy the image onto your Clipboard.
2. Open the artifact in Blueprint where you want to paste the image. Click the canvas to place focus on the canvas.
3. Click the canvas to place focus on it.
4. Click the **Paste** button on the ribbon (*Home* tab, *Clipboard* group) or use the **Ctrl-V** keyboard shortcut.

Importing and Exporting

Blueprint allows you to import and export data using a variety of methods.

Blueprint allows you to import:

- textual requirements from Microsoft Excel
- glossary terms from Microsoft Excel
- Visio diagrams

Blueprint allows you to export:

- artifacts to an Office Document
- artifacts to an ALM target
- test plans to Excel or an ALM target

About Excel update

Note: You can only use this feature if it has been enabled by your instance administrator and if you have the correct project role and project role assignment.

Blueprint allows you to efficiently edit artifacts in Microsoft Excel spreadsheet format and import your updates into Blueprint. There are two methods of updating artifacts using Excel: using an Excel update template generated within Blueprint or creating your own update template.

With the first method, Blueprint gives you the ability to generate an Excel list of artifacts from any single project in Blueprint and then make your changes to the list in Excel. For more information on generating an Excel update template, see [About generating an Excel update template](#)

Alternately, you can create and edit your own update template. For more information on creating your own update template and meeting the formatting requirements, see [About Excel update](#).

For more information about updating an artifact list, see [Updating artifacts using Excel](#).

Note: Only **.xlsx** files can be used to edit artifacts and import the updates into Blueprint.

Formatting requirements

Before editing or creating a spreadsheet to update artifacts, you should familiarize yourself with the formatting specifications below.

Important: The only property that is required in your spreadsheet is the artifact ID. You must specify the *ID* column in the first or second row. Next, list the artifact ID(s) you need to edit below, as the following image demonstrates.

	A
1	
2	ID
3	3473676
4	3505496
5	3501861

Only the *ID* header and artifact ID numbers are required. Do not specify prefixes. For example: For the artifact ID **UC12345**, only specify **12345**.

This image shows which properties you have the option of specifying and which fields are read-only:

	A	B	C	D	E	F	G	H
1	Property to Update	Yes		Yes		No	Yes	No
2	Artifact to Update	Version	ID	Name	Artifact Type	Description	Custom Property 1	Custom Property 2
3	Yes		xx0					
4	No		xx1					
5	Yes		xx2					
6	No		xx3					
7	Yes		xx4					
8	No		xx5					
9	Yes		xx6					
10	No		xx7					
11	Yes		xx8					
12	No		xx9					
13	Yes		10					
14	No		11					
15	Yes		12					
16	No		13					
17	Yes		14					
18	No		15					
19	Yes		16					
20	No		17					
21	Yes		18					
22								
23						Mandatory		
24						Optional		
25						Non-Functional / Read Only		

Note: If version numbers are not specified in the spreadsheet, the updates you performed in Excel will override the latest version(s) of the artifacts when you import the Excel file into Blueprint.

Specifying custom property values

When you are specifying a custom property value within your spreadsheet, use the following punctuation to differentiate multi-choice custom properties from single-choice custom properties:

Value	Description	Example
,	Commas specify and separate multi-choice values.	High,Medium,Low (The multi-choice values above belong to an example priority property, <i>Project Risk</i> .)
""	Quotations preserve the content within them. Tip: To use a comma in a single-choice property, wrap your value in quotations.	"Smith, Joan" (The single-choice value above belongs to an example custom property called <i>Full name</i> .)

About generating an Excel update template

Blueprint allows you to [generate an Excel update template](#) from any project. In every generated Excel update template, each row contains information about the artifact that you can edit. Each column contains property information that you can edit as well. The template contains update variables in the first row and column, as the image below shows:

Change this variable to Yes when updating a property in the column.

Change this variable to Yes when updating information in this row.

	A	B	C	D	E	F
1	Property to Update			No	No	No
2	Artifact to Update	Version	ID	Name	Artifact Type	Description
3	No	1	3473676	Submissions	Folder	
4	No	2	3505496	Credit Card Application	Textual	
5	No	1	3501861	Requirements	Folder	
6	No	2	3473675	Non-functional requirements	Folder	
7	No	2	3473674	Technical and data requirements	Folder	
8	No	2	3473678	Examples	Folder	
9	No	2	3473677	Glossary	Folder	

When you update any row in the file, you also need to change the update variables in the same row and column to **Yes**. This allows Blueprint to recognize that you want to update the associated artifact.

Note: Empty update fields trigger updates by default.

Example

Jorges, a product manager, has generated an Excel update template with the goal of quickly updating his Blueprint project using Excel. He wants to make the following changes to his artifact list: renaming **Credit Card Application** to **Credit Card Application Process** and **Technical and data requirements** to **Data requirements**. To trigger updates, he also needs to change the update variables to **Yes**. Here are the changes he made to the generated Excel update template:

	A	B	C	D	E	F
1	Property to Update			No	No	No
2	Artifact to Update	Version	ID	Name	Artifact Type	Description
3	No	1	3473676	Submissions	Folder	
4	Yes	2	3505496	Credit Card Application Process	Textual	
5	No	1	3501861	Requirements	Folder	
6	No	2	3473675	Non-functional requirements	Folder	
7	No	2	3473674	Technical and data requirements	Folder	
8	No	2	3473678	Examples	Folder	
9	No	2	3473677	Glossary	Folder	

About exporting and importing rich text formatting using Excel update

Microsoft Excel does not support certain rich text styles. Therefore, certain rich text formatting cannot be successfully exported from Blueprint using Excel update template generation, nor imported back into Blueprint.

The following table identifies which types of rich text formatting you can successfully export from Blueprint in an Excel update template or import into Blueprint using **Excel Update**:

Rich text feature	Generating an Excel update template (exporting)	Importing an Excel update into Blueprint
Font family	✓	✓
Font color	✓	✓
Font size	✓	✓
Bold	✓	✓

Italic		
Underline		
Horizontal alignment		
Hyperlink		
Subscript		
Superscript		
Strike-through		
Bullets and numbered lists		
Tables	 *	
Background color		

*Table cells are divided into separate tabs within Excel.

Updating artifacts using Excel

Blueprint allows you to efficiently edit artifacts in Microsoft Excel spreadsheet format and import your updates into Blueprint. There are two methods of updating artifacts using Excel: using an Excel update template generated within Blueprint or creating your own update template.

With the first method, Blueprint gives you the ability to generate an Excel list of artifacts from any single project in Blueprint and then make your changes to the list in Excel. For more information on generating an Excel update template, see [About generating an Excel update template](#)

Alternately, you can create and edit your own update template. For more information on creating your own update template and meeting the formatting requirements, see [About Excel update](#).


To update a project using Excel, perform the following steps:

1. Create a new spreadsheet in Excel or generate an Excel update template in Blueprint.

For more information on formatting your own spreadsheet, see [Formatting requirements](#).

To generate an Excel update template:

1. Open the project containing the artifacts you want to update.
2. Click the **Generate Excel Update Template** button.



The *Save As* dialog appears.

3. Enter a name for the file, choose a location to save the file and then click **Save**.

The Excel update template starts downloading.

4. Open the Excel file.


2. Update the Excel template as needed.

For information on updating a generated Excel update template, see [About generating an Excel update template](#).

Note: When making changes to the artifact list, you must change the value in the header row and the header column to **Yes**.

3. Click **Save**.
4. Import the changes into your Blueprint project.
 1. Click **Excel Update** (*Import/Export* tab, *Import* group).

The *Update Artifacts from Excel* dialog appears.



2. Select the project in the list you want to update and then click **OK**.

The *Select File to Update* dialog appears.

3. Click the **...** button, select the file to update and click **OK**.
4. Click the **Upload** button.

Any errors or warnings appear in the list below.

Tip: You can export the list of errors and/or warnings to a CSV file by clicking **Export to CSV**.

5. Click **Update**.
The update summary screen appears.
6. Click **Close**.

Note: Artifact updates are automatically saved but not published. To publish all changes you have made, click **Publish All**.

Generating an Excel update template


Blueprint allows you to generate an Excel update template from a single project. The generated Excel template contains a list of artifacts that you can arrange in whatever way you want them to appear in your template.

To generate an Excel update template, perform the following steps:

1. Open the project containing the artifacts you want to update.
2. Arrange the list of artifacts in the way you want them to appear in your generated template.

Note: Make sure to save any changes you have made that you want to appear in the Excel update template.

3. Click the **Generate Excel Update Template** button.



The *Save As* dialog appears.

4. Enter a name for the file, choose a location to save the file and then click **Save**.

The file downloads successfully. Now you can perform your updates to the template within Excel. For more information about updating artifacts using your template in Excel, see [Updating artifacts using Excel](#).

Importing new requirements from Microsoft Excel

Blueprint provides you with the ability to import requirements from a Microsoft Excel spreadsheet. In other words, you can create your requirements in Microsoft Excel and then import them into Blueprint.

Note: You cannot undo an import from Excel. You can, however, delete the imported requirements.

Blueprint provides the following features to make importing requirements easier:

- A preview of the requirements are displayed prior to performing the actual import operation.
- A list of any mismatches, between the Excel spreadsheet and the Blueprint project, in terms of Artifact Types, Properties, or Valid Values. The list identifies the column/row in the spreadsheet so you can fix the error prior to importing.

- Blueprint allows you to select the project, and the folder or parent requirement under which you want to import the requirements. After the import is complete, you can drag and drop requirements to adjust the hierarchy.

Tip: To better visualize where the requirements will be imported, we recommend that you turn off **Wrap Text** (View tab, *Artifact List* group) option on the ribbon, and select the folder or parent requirement under which you want the new requirements to be imported.


Sample Import Spreadsheets

For your convenience, take a look at the following examples:

- [Requirement Import Template](#): Provides a basic template with only system properties. This template will work with all Blueprint projects.
- [Sample Requirement Import](#): Provides an example with hierarchy columns, custom artifact types, and custom properties. Here are a few important details to keep in mind while you are looking at this template:
 - The Hierarchy column (and blank columns to the right of it) are optional: depending on where + symbol is, the artifacts will be made children
 - In this template, the values in the Artifact Type column are custom artifact types. This template will not work unless the project contains Artifact Types called Business Rule and Business Requirement.
 - Additional columns (example: Priority, Effort in Days) are custom properties and must exactly match the name of the custom property in your project.

Excel Spreadsheet Format

Each new requirement that you want to import must appear as a new row in the spreadsheet. The Excel spreadsheet looks like this:




1	A	B	C	D	E	F	G	H
	Hierarchy			Name	Artifact Type	Description	Priority	Effort in Days
2	+			Credit Card Process Improvements	Process Improvement	We do a good job at notifying customers when their Credit Card is approved. We need to improve and ensure our Standard Operating Procedure (SOP) is met and customers are notified within 2 business days when their Credit Card As part of the Business Analysis, collect the average time to carry out each step in the Credit Card management process	High	0
3		+		Rejection Notice	Business Rule		High	0
4		+		Process Timing Report	Process Improvement		Medium	0
5		+		Identify Tasks for Improvement	Process Improvement		Medium	0
6			+	Reduce Manual Tasks	Process Improvement	Identify any steps in the Credit Card management process that are purely manual (not supported by any bank	Medium	2
7			+	Identify Non Enterprise Tasks	Process Improvement	Identify any steps in the Credit Card management process that still utilize the mainframe.	TBD	0
8								
9								

The following columns can be included in the Excel spreadsheet:

Spreadsheet Column Name	Description	Required or Optional	Valid Values
Hierarchy	You can use Hierarchy columns to specify the relative outline level at which each Textual Requirement will be imported. When no Hierarchy is specified, all requirements are imported at the same hierarchy level.	Optional	The plus sign, + , must appear in the appropriate column depending on the desired hierarchy.
Name	Defines the name of the requirement.	Required	Specify the text that you want to import as the name of the new requirement.
Artifact Type	Defines the artifact type.	Required	This value must be an artifact type that exists in the project to which you are importing. In other words, requirements are only imported when matching artifact types have been configured by the project admin in the Blueprint project.
Description	Defines the description of the requirement.	Optional	Specify the text that you want to import as the description of the requirement.
Custom Artifact Properties (example: Priority, Owner)	Allows you to import values for custom properties in your project.	Optional	Other Excel columns, such as Priority or Effort in Days, will only be imported when matching Properties and Valid Values have been configured by the Project Admin in the Blueprint project.

To import new requirements from Microsoft Excel:

1. Create your [import spreadsheet](#) using Microsoft Excel. Save the document as a **.xlsx** file.
2. Click the **Artifacts** button on the ribbon (*Import/Export* tab, *Import* group).
3. Select the project to which you want to import the requirements. Click **Next**.
4. Select the folder or parent requirement under which you want to import the requirements. Click **Next**.
5. Click the  button and locate the **.xlsx** file that contains your requirements.
 A list of any mismatches, between the Excel spreadsheet and the Blueprint project, in terms of artifact types, properties, or valid values. The list identifies the column and row in the spreadsheet so you can fix the error prior to importing. You must correct all validation errors before you can import the requirements. You can click the **Validate** button at any time to re-validate the import data.
 When the data is validated without any errors, click **Next**.
6. Read the import summary to verify that the requirements are going to import as expected. To continue, click **Next**.
 A status summary is displayed.
7. Click **Finish** to close the dialog.

After the requirements are imported, they appear as unpublished and unsaved artifacts. You must publish these artifacts before other users can view them. You can discard the changes if you notice a problem with the import.

Tip: You can also update your requirements artifacts using Excel. For more information about using Excel to update artifacts, see [Updating artifacts using Excel](#).


Importing glossary terms from Microsoft Excel

Blueprint provides you with the ability to import glossary terms from a Microsoft Excel spreadsheet. In other words, you can create your glossary terms in Microsoft Excel and then import them into Blueprint.

Important: You must open a glossary artifact before the **Glossary Terms** button becomes accessible on the ribbon (*Import/Export* tab, *Import* group).

To get started, simply [download the glossary term import template](#) and add your glossary terms and definitions on a new row.

To import glossary terms:

1. Create your [import spreadsheet](#) using Microsoft Excel. Save the document as a **.xlsx** file.
2. Open a glossary artifact
3. Click the **Glossary Terms** button on the ribbon (*Import/Export* tab, *Import* group).
4. Click the  button and locate the **.xlsx** file that contains your glossary terms.

A list of any validation errors is displayed. You must correct all validation errors before you can import the textual requirements. You can click the **Validate** button at any time to re-validate the import data.

When the data is validated without any errors, click **Next**.

5. Read the import summary to verify that the glossary terms are going to import as expected. To continue, click **Next**.


A status summary is displayed.

6. Click **Finish** to close the dialog.

After the glossary terms are imported, the glossary artifact contains unsaved and unpublished changes. You must publish the artifact before other users can view the new glossary terms. You can discard the changes if you notice a problem with the import.

Exporting an artifact list view to Excel


Blueprint allows you to conveniently export your artifact list view to a Microsoft Excel document (.xls format).



Collapsed and expanded artifacts

When you export your artifact list view, the generated Excel document lays out your artifacts as they appear in Blueprint.

If you expand any parent artifacts before exporting your list view, their children appear in the generated Excel document.



Name	ID	Description
Executive Sponsor Interview	PF4668403	Sr. VP Credit Card Operations
Online Application for Credit Card	BR4668412	Customers currently have to go into a bank branch office to apply for Credit Cards. Add to the existing Online Banking website, the ability to Apply for a Credit Card online.
Credit Card Process Improvements	PI4668414	

If you collapse any parent artifacts before exporting your list view, their child artifacts do not appear in the generated Excel document.

Preserved column details

When you export your artifact list view to Microsoft Excel, the following aspects of your artifact list are preserved:


- Name
- ID
- Description
- Artifact Type
- Any custom properties you have in your view

Indicators (that is, icons for trace relationships, comments, attachments and follows that link to related data in Blueprint) are not preserved.

Microsoft Excel preserves certain rich text formatting. For information about rich text formatting Microsoft Excel preserves, see [About exporting and importing rich text formatting using Excel update](#).

To export your artifact list view to Microsoft Excel:

1. Expand and collapse items in your artifact list so it is displaying the content that you want included in your generated Excel document.
2. Click the **Artifact List View** button on the ribbon (*Import/Export* tab, *Export* group).



The **Save As** dialog box appears.

3. Name the file with an **.xls** extension in your preferred location and then click **Save**.

After the document has generated successfully, you can find the new Excel document at the output location that you specified.

Tip: To open the **.xls** file, launch Microsoft Excel and then click **File > Open**. Alternatively, you can right click the **.xls** file and click **Open with > Microsoft Excel**. If you attempt to open the **.xls** file from your browser, you may experience issues.

About ALM integration

ALM integration allows you to export artifacts to an ALM (Application Lifecycle Management) system. Your project administrator must setup an ALM Target and grant you access to the target before you can export artifacts to an ALM system.

Read the [example](#) below to learn more about ALM integration works in Blueprint.

What data is exported to the ALM system?

The following data is exported:

- artifact data (example: name, description, and other properties including custom properties)

Note: The way in which artifact types and artifact properties are mapped depends on how the ALM target is configured in Blueprint. The artifact types and properties must be mapped in order to export the data.

- sub-artifact data

Note: The concept of sub-artifacts is not preserved in the ALM system after the export. Any data related to a sub-artifact in Blueprint is rolled up to the artifact level in the ALM system. For example, if a shape (sub-artifact) in a diagram contains file attachments, the files are exported but they are associated with the artifact.

- artifact attachments (assuming this is option is configured in the ALM target)
- artifact traces (assuming both of the traced artifacts are exported to ALM)
- diagram image (for UI mockups, business process diagrams, domain diagrams, generic diagrams)
- each artifact that is exported to an ALM system contains a hyperlink to the original artifact in Blueprint.

The following data is not exported:

- comments
- version history
- traces (if both artifacts are not in the ALM system)

Example

Exporting artifacts for the first time

Let's start by creating a new **Login** folder in Blueprint and then creating 3 new artifacts:

- **Login** (textual requirement artifact)
- **Login Use Case** (use case artifact)
- **Login Page** (document artifact with a .jpg file)

After the new artifacts are published, the artifact list looks like this:

Test >
PF20608: Login

Name	ID	Description	Artifact Type
Login Page	DOC20609		Document
Login	RQ20610	The login page shall authenticate the use	Textual Requirement
Login Use Case	UC20611		Use Case

Now we will use the ALM Export feature to export these artifacts to the ALM system. The export settings used are:

- Publish all artifacts selected
- Publish Path: Requirements\Export_Mar17

The *Change Summary* screen in the *ALM Export Wizard* looks like this:

Adding (4)	Updating (0)	Deleting (0)
Id	Name	Action
PF20608	Login	Details
DOC20609	Login Page	Details
RQ20610	Login	Details
UC20611	Login Use Case	Details

As you can see in the *Change Summary* image, there are 4 new artifacts being exported to the ALM System (the Login folder and the 3 new artifacts).

After the export is complete, here is what the new items look like in HP ALM:

Export_Mar17	---	aglaizel	3666
Login	Not Covered	aglaizel	3667
Login Page	Not Covered	aglaizel	3668
Login	Not Covered	aglaizel	3669
Login Use Case	Not Covered	aglaizel	3670

Description	Comments	Rich Text	Attachments	History
<p>The login page shall authenticate the user if the username and password are correct.</p>				

Exporting artifact changes and deletions

Now, lets make the following modifications in Blueprint:

- update the description of the **Login** textual requirement.
- create a new UI mockup called **Login Mockup**
- delete the **Login Page** document artifact

After the changes are made, the artifact list looks like this:

Test >
PF20608: Login

Name	ID	Description	Artifact Type
Login	RQ20610	The login page shall authenticate the use	Textual Requirement
Login Use Case	UC20611		Use Case
Login Mockup	UM20615		UI Mockup

Now we will use the ALM Export feature to export these artifacts to the ALM system. The export settings used are:


- Publish all artifacts that changed since last publish, 3/17/2012 1:28PM
- Export Path: Requirements\Export_Mar17

The *Change Summary* screen in the *ALM Export Wizard* looks like this:

Adding (1) Updating (1) Deleting (1)		
Id	Name	Action
UM20615	Login Mockup	Details

As you can see in the *Change Summary* image, the export to the ALM System includes 1 added artifact, 1 updated artifact, and 1 deleted artifact.

After the export is complete, the new items appear in HP ALM v11:



Artifact Name	Status	Owner	ID
Login	Not Covered	aglaizel	3666
Login	Not Covered	aglaizel	3667
Login Use Case	Not Covered	aglaizel	3669
Login Use Case	Not Covered	aglaizel	3670
Login Mockup	Not Covered	aglaizel	3671

Description: The login page shall authenticate the user if the username and password are correct. Otherwise, an error shall display.

As you can see in the image above, the **Login Page** item is deleted, the **Login Mockup** has been added, and the description of the **Login** requirement has been updated.

Exporting artifacts to an ALM Target

Overview

You can export artifacts to an ALM system if your project administrator has [configured an ALM Target](#) and [granted you access](#) to it.


Exporting artifacts to an ALM target is an operation that consists of the following two jobs:

1. [Setting up the export](#)
2. [Performing the export](#)

Setting up the export

To set up the export to an ALM target:

1. Click the **ALM Export** button on the ribbon (*Import/Export* tab, *Export* group).
The *Source Project* screen of the *ALM Export Wizard* appears.
2. Select the project that contains the artifact(s) you want to export to an ALM target, and then click **Next**.
The *Select Target* screen appears.
3. Select the target that you want to export the artifacts to, modify the export options, and then click **Next**.
The following options can be set:
 - What would you like to do?
 - **Export all artifacts that changed since last publish:** Allows you to export all artifacts that have changed since the last export.
 - **Export all artifacts selected:** Allows you to export only the selected artifacts.

- **Export Path:** Defines the path in the HP ALM system where the artifacts will be exported. To change the path, click the  button to open the *Location Picker* dialog. The *Location Picker* dialog displays the directory structure of your ALM system. Choose the directory where you want to export the artifacts and then click **OK** to close the dialog.

Note: This option is only available for HP ALM targets.

- **Generate images for document output:** Defines whether or not you want to generate images for graphic artifacts that you are exporting, such as diagrams. If this option is disabled, images are not exported.

If this option is disabled, images (that is, graphic artifacts) are not exported to the ALM system.

After you click **Next**, the *Select Revision* screen appears.

4. Select whether you want to export data from live artifacts, or data from a baseline or review and then click **Next**.

The *Artifacts to Export* screen appears.

5. Select the artifacts you want to export and click **Next**.

Select the artifact(s) that you want to include in the document. Simply select the artifacts and click the **Add** button.


The *Map Area Path* screen appears if you chose a TFS target.

6. Specify the area path to which the artifacts should be exported and click **Next**.


This option is only applicable when you are exporting to a TFS target. This option is not applicable for ALM targets.

After you click **Next**, your setup job is scheduled to run in the queue.

To check the status of your job: click the **Menu** button (on the ribbon), point to *Manage* and then click **Job Management**.

When the status of your job changes, a **notification** icon () appears in the lower left corner of the screen. When your job has completed, click the **Completed** status in the notification to proceed to the next step: [Performing the export](#).

Performing the export

When your [setup job](#) has completed successfully, a **notification** icon () appears in the lower left corner of the screen. Click the **Completed** status in the notification to complete this step.

To perform the export to an ALM target:

1. Resolve conflicts and verify the summary of changes is correct.

The *Change Summary* screen provides you with the total number of artifacts that you are adding, updating and deleting from the ALM system. You can click the **Details** link to view information about the property mappings.


Conflicts occur when you attempt to export an artifact that have changed in the ALM system since the last update. You have the option to keep the version in the ALM system or overwrite it. To resolve conflicts, select all or some of the artifacts using the check box on the left side of the screen and then click the

Resolve Selected Conflicts button. When the *Resolve Conflict* dialog appears, choose **Overwrite** or **Keep** and then click **OK**.


2. Click **Finish** to export the artifacts.

After you click **Finish**, your export job is scheduled to run.

To check the status of your request: click the **Menu** button (on the ribbon), point to *Manage* and then click **Job Management**.

When the status of your job changes, a **notification** icon () appears in the lower left corner of the screen. When your job has completed, click the **Completed** status in the notification.

A dialog appears, showing your export status.



Blueprint provides you with the option of saving this message to a **.csv** file.

About Visio integration

Blueprint supports the ability to import and export Microsoft Visio diagrams.

About importing Visio diagrams

You can import Visio diagrams into the following artifact types:

- Generic diagram
- UI mockup
- Business process diagram

When you import a Visio diagram, Blueprint substitutes your Visio shapes with matches that exist on the palette. In cases where a suitable Blueprint shape does not exist, the original Visio shape is imported as an *external shape*.

Note: Blueprint does not currently support importing rich text formatting in shapes from Visio. Instead, text is imported with plain text formatting.

About External Shapes

An *external shape* is a Microsoft Visio shape that has been imported as a vector or bitmap image and has not been replaced by an equivalent shape on the Blueprint palette.

The differences between vector images and bitmap images are as follows:

Vector	Bitmap
<ul style="list-style-type: none">■ Has a transparent background	<ul style="list-style-type: none">■ Has an opaque background
<ul style="list-style-type: none">■ Quality is not diminished when the image is resized	<ul style="list-style-type: none">■ Quality is diminished when the image is resized
<ul style="list-style-type: none">■ Can be edited with the following tools:<ul style="list-style-type: none">■ Drawing tools (<i>Editor Tools</i> tab, <i>Drawing</i> group)■ Font tools (<i>Editor Tools</i> tab, <i>Font</i> group)■ Paragraph tools (<i>Editor Tools</i> tab, <i>Paragraph</i> group)	<ul style="list-style-type: none">■ Image cannot be edited using the following Blueprint tools:<ul style="list-style-type: none">■ Drawing tools (<i>Editor Tools</i> tab, <i>Drawing</i> group)■ Font tools (<i>Editor Tools</i> tab, <i>Font</i> group)■ Paragraph tools (<i>Editor Tools</i> tab, <i>Paragraph</i> group)
<ul style="list-style-type: none">■ Is suited for print For more information about exporting a diagram for print, see Exporting a diagram to Visio.	<ul style="list-style-type: none">■ Print quality is diminished

About exporting Visio diagrams

You can export any of the following diagrams in Visio 2010 or 2013:

- Generic diagrams
- UI mockups
- Business process diagrams
- Use case diagrams
- Storyboard diagrams

Blueprint exports diagrams in Visio drawing format, **.vsd** or **.vsdx**.

Importing a Visio diagram

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

You can import Visio diagrams into the following artifact types:

- Generic diagram
- UI mockup
- Business process diagram

When you import a Visio diagram, Blueprint substitutes your Visio shapes with matches that exist on the palette. In cases where a suitable Blueprint shape does not exist, the original Visio shape is imported as an *external shape*.

Note: Blueprint does not currently support importing rich text formatting in shapes from Visio. Instead, text is imported with plain text formatting.

Requirements

To import a Visio diagram, you require the following:

- Elevated trust in-browser
- Blueprint version 5.1.2 and later
- Microsoft Visio 2010 or 2013 must be installed.

To import a Visio diagram:

1. Save the document containing the diagram on your computer as a **.vsd** or **.vsdx** file.

Note: Only **.vsd** or **.vsdx** files can be imported.

2. In Blueprint, open the artifact to which you want to import the Visio diagram.
3. Click the **Visio Diagram** button on the ribbon (*Import/Export* tab, *Import* group).



The open dialog box appears.

4. Select the Visio diagram you want to import and then click **Open**.


The diagram appears in the main content area.

Upon importing a diagram, Blueprint replaces the diagram's shapes with equivalent Blueprint shapes. In certain cases, imported shapes have no equivalents on the Blueprint palette.


Tip: By using the **External Shapes** indicator, you can identify imported shapes that have not been replaced with Blueprint shapes.

To identify an external shape:

- Select the **External Shapes** check box on the ribbon (*View* tab, *Show Indicators* group):



Indicators appear next to all external shapes in your diagram.



Exporting a diagram to Visio

Important: This feature is only available if Blueprint is configured to run with elevated in-trust browser.

You can export any of the following diagrams for use in Microsoft Visio 2010 or 2013:

- Generic diagrams
- UI mockups
- Business process diagrams
- Use case diagrams
- Storyboard diagrams

Blueprint exports diagrams in Visio drawing format, **.vsd** or **.vsdx**.

Requirements

To export a diagram to Visio, you require the following:

- Elevated trust in-browser
- Microsoft Visio 2010 or 2013
- Blueprint version 5.1.2 and later

To export your Blueprint diagram to a Visio .vsd file:

1. In Blueprint, click the **Visio Diagram** button on the ribbon (*Import/Export* tab, *Export* group).

The save dialog box appears.



Important: If you want to import your Blueprint diagram into an existing Visio document, make sure the Visio document is closed.


2. Enter a filename for your export diagram and then click **Save**.

You have successfully exported your Blueprint diagram to a Visio file.

About artifact printing

Overview

Blueprint allows you to efficiently print individual artifacts in Microsoft Word and PDF files. You can print the latest version of an artifact or choose a specific version to print.



Output file

If you are using the default print template, your output file contains the following information about the artifact:

- Artifact ID
- Artifact name
- Artifact type
- Artifact URL
- Version number
- Description
- Created By
- Created On
- Last Edited By
- Last Edited On
- Any custom properties
- Any trace relationships

Your artifact data is laid out in a table (see images below).

RQ4668419.docx - Microsoft Word

File Home Insert Page Layout References Mailings Review View Blueprint Blueprint Manager

RQ4668419: Identify Non Enterprise Tasks [Textual Requirement]

Original Artifact: <http://today/default.aspx?ArtifactId=4668419>
Version: 10

Description:
 Identify any steps in the Credit Card management process that:

- Still utilize the mainframe
- Can not be carried out remotely over the Internet

Name	Value
ID	RQ4668419
Name	Identify Non Enterprise Tasks
Created By	Christina McNish
Created On	21/02/2013 9:19:28 AM
Last Edited By	Christina McNish
Last Edited On	08/04/2013 11:08:31 AM

Custom Properties

Acceptance Criteria

Priority

Effort in Days 0

Attachments:
 expand2.xls

Related Artifacts:

Direction	Name	Relationship Type
From	FR4668425: Transfer Funds	Manual
To	DOC4944639: New Document 1	DocumentReference

Page | 1

Page: 1 of 2 Words: 98 90%

RQ4668419 (1).pdf - Adobe Reader

File Edit View Window Help

1 / 1 69.6% Comment Share

RQ4668419: Identify Non Enterprise Tasks [Textual Requirement]

Original Artifact: <http://today/default.aspx?ArtifactId=4668419>
Version: 8

Description:
 Identify any steps in the Credit Card management process that:

- Still utilize the mainframe
- Can not be carried out remotely over the Internet

Name	Value
ID	RQ4668419
Name	Identify Non Enterprise Tasks
Created By	Christina McNish
Created On	21/02/2013 9:19:28 AM
Last Edited By	Christina McNish
Last Edited On	08/04/2013 9:55:19 AM

Custom Properties

Acceptance Criteria

Priority

Effort in Days 0

Attachments:
 expand2.xls

Related Artifacts:

Direction	Name	Relationship Type
From	FR4668425: Transfer Funds	Manual
To	DOC4944639: New Document 1	DocumentReference
To	DOC4734331: Document -VideoDemo	DocumentReference


Page | 1

Blueprint supplies a default template that structures your artifact for printing. The default print template is accessible at the project level as well as at the instance level.

Modifying the default print template at the project level

Blueprint provides [project administrators that have the applicable privileges](#) with a default Word template for the purpose of exporting and printing artifacts.

The template is written and designed using the document template authoring add-in.



We do not recommend making changes to the template directly unless you have document template authoring experience. For more information about document template authoring, see the [Document Template Authoring Help](#).

Note: The default print template can be changed at two different levels of administration privileges. Instance administrators with the applicable privileges can modify the default print template within the *Instance Administration Console*, setting a new default template for all projects. Both instance administrators and project administrators with the applicable privileges can change the default print template within the *Project Administration Console*, which sets a new print template for that individual project only.

Once you change the print template at the project level, changes to the template at the instance level do not override the project level template.

To modify the default print template:

1. Open the *Project Administration Console*.
2. Click the *Project Print Template* link.

Important: To restore the system default document template later on, it is a good idea to click the **Download** link to save a copy of the default document template locally. When you want to restore the system default document template, you can simply click the **Replace** link to upload it. If you do not save a copy of the system default document template and you use the **Restore** operation, you will restore the latest document template that has been uploaded by the instance administrator.

3. Create a new template or modify an existing document template.

If you want to modify the existing template, click the **Download** link.

Note: If you are using Internet Explorer 8, you must enable the *automatic prompting for file downloads* security setting before you can download the file from Blueprint. To enable this setting, click **Tools > Internet Options > Security > Custom level... > Downloads** and then enable the **Automatic prompting for file downloads** option.

If you want to change the scale of rich text font size to improve print quality, you can select a different percentage.

4. Click the **Replace** link.

The *save* dialog box appears.

5. Select your new print template and then click **Open**.
6. Click **Save**.

Your new print template is saved. Whenever you click the **Print to PDF** button or the **Print to Word** button on the ribbon (*Home* tab), your print template is used to export an artifact to a file for printing purposes.

Printing a historical version of your artifact

Note: Before printing, make sure to save and publish your artifact.

To print a specific version of your artifact:

1. Click the artifact version you want to print (*History* tab).

The artifact details appear in the main content area.

2. Select *Print to PDF* and then click **Print to Word** (*Home* tab, *Artifacts* group).

Your artifact appears in a Word file.

In Word, you can perform any stylistic edits and print the artifact with your preferred settings.

3. Print your Word artifact.

On the *File* menu, click **Print**.

When the print dialog box appears, click **OK**.

Printing an artifact to a PDF document

Note: Before printing, make sure to save and publish your artifact.

To print your artifact to a PDF document:

1. Click the artifact you want to print.
The artifact details appear in the main content area.
2. Select *Print to PDF* and then click **Print to PDF** (*Home* tab, *Artifacts* group).
Your artifact appears in a PDF file.
3. Print your PDF artifact.
On the *File* menu, click **Print**.
When the print dialog box appears, click **OK**

Printing an artifact to a Word document

Note: Before printing, make sure to save and publish your artifact.

To print your artifact to a Word document:

1. Click the artifact version you want to print (*History* tab).
The artifact details appear in the main content area.
2. Select *Print to PDF* and then click **Print to Word** (*Home* tab, *Artifacts* group).
Your artifact appears in a Word file.
In Word, you can perform any stylistic edits and print the artifact with your preferred settings.
3. Print your Word artifact.
On the *File* menu, click **Print**.
When the print dialog box appears, click **OK**.

About job management

After you start a job, your job is placed in the *Job Management* queue. Jobs are processed according to their order in the queue. With the *Job Management* feature, Blueprint provides you with the ability to view and manage any of your jobs. A variety of operations can be applied to jobs, helping to manage the queue. For example, when a job has failed or terminated, you have the option of restarting the job or removing the job from the queue.

Instance administrators with the [correct privileges](#) can manage any job within the instance.

The *Job Management* dialog contains the following columns:

Column Name	Description
Job Id	Indicates the ID of the job.
Start	Indicates the date and time the user started the job.
End	Indicates the date and time the job completed, failed or terminated.
User	Indicates the user that started the job.

Job Type	Indicates the type of job that was executed. To view a complete list of jobs that can be performed, see Job types .
Project	Indicates the ID and name of the project within which the job was executed.
Status	Indicates the status of the job. To learn more about job statuses, see Job statuses .

Tip: The *Job Management* list can be filtered the same way as an artifact list. For more information about filtering a list, see [View management and saved views](#).

When you select a job in the queue, the *Details* pane on the right populates with information about the job, including processing details.

The *Details* pane contains the following information:

- **Job Id:** Indicates job ID number.
- **Submitted Date/Time:** Indicates the date and time the system started processing the job.
- **Job Start Date/Time:** Indicates the date and time the user started the job.
- **Job End Date/Time:** Indicates the date and time the job completed, failed or terminated.
- **Job Owner:** Indicates the user that started the job.
- **Status:** Indicates the status of the job. To view a list of statuses, see [Job statuses](#).
- **Job Type:** Indicates the type of job that was executed. To view a list of jobs that can be performed, see [Job types](#).
- **Project:** Indicates the ID and name of the project the user executed the job in.
- **Service:** Indicates the service that executed the job.
- **Progress:** Indicates the percentage of job completion.

Note: Below the *Progress* field, the *Details* field contains processing details about the job.

Job types

The following types of jobs can be performed:

■ Document Generation

You can export artifact data to a Microsoft Word or Microsoft Excel document, assuming your project administrator has added templates to the project. For more information on generating a document, see [Generating an office document](#).

■ ALM Export

If your Project Administrator has set up an ALM target and you have an author license, you can export artifacts to an ALM target.

Exporting artifacts to an ALM target is a two-step process that is divided into the following jobs:

- [Setting up the export](#)
This job appears in the *Job Management* dialog as a **Change Summary** (*Job Type* column).
- [Performing the export](#)

For more information on exporting artifacts to an ALM target, see [Exporting artifact\(s\) to an ALM target](#).

■ Test Plan Export

When a test plan project contains an ALM target, the test plan(s) export to ALM is processed as a job. For more information on test generation, see [Generating a test plan](#).

Job operations

Depending on your job type and status, some of the following operations are available:

■ Cancel

When your job is running, you have the option of canceling it.

■ Remove

When a job has failed, terminated or completed, you can remove the job from the queue.

■ Restart

When a job has failed or terminated, you can restart the job.

■ Show Result

If the job is a document generation, you can click **Show Result** to see the artifact that contains the document output.

The screenshot shows the 'Job Management' window. On the left is a table with columns: Job ID, Start, End, User, Job Type, Prc, and Status. The table lists 26 jobs, all with a status of 'Completed'. On the right is a 'Details' panel for Job ID 269. It shows: Submitted Date/Time: 1/15/2015 2:46:35 PM, Job Start Date/Time: 1/15/2015 2:46:46 PM, Job End Date/Time: 1/15/2015 2:54:46 PM, Job Owner: Default Instance Admin, Status: Completed, Job Type: HP ALM REST Export, Project: PR153303: Test Project for ALM Export, Service: Blueprint Job Service (qa_1x64)@PRDWB, and Progress: 100%. Below the progress bar, it says: 'Started the first ALM export. Exported 9/9 artifact(s). Exported traces for 9/9 artifact(s). Finished ALM export.'

Instance administrators with the [correct privileges](#) can apply the above operations to any job within the instance when the operation is available.

Tip: To view the most updated version of the queue, click **Refresh**.

Job statuses

A job can have one of the following statuses:

Status	Reason
Scheduled	The job has been placed in the queue. Any jobs that are ahead of your job in the queue will be processed first.
Running	The job is currently being processed.

Canceling	The cancel operation is being processed.
Cancel Requested	The client submitted a cancel operation to the server.
Completed	The job has successfully completed.
Terminated	The job has been canceled, either by you or an Instance Administrator. If an Instance Administrator has canceled the job, you can view details of the cancellation at the bottom of the <i>Details</i> pane.
Failed	The job has not completed successfully. The <i>Details</i> pane in the <i>Job Management</i> dialog provides high-level logs for troubleshooting.

To open Job Management:

- Click the **Menu** button, point to *Manage* and then click **Jobs**.

The *Job Management* dialog appears.

Canceling a job

Blueprint allows you to cancel any jobs you have scheduled to run or are currently running. After you cancel a job, the job remains in the queue. Blueprint also provides you with the option of restarting the job after it has been canceled.

Note: Instance administrators with the [correct privileges](#) can cancel any running or scheduled job in the instance.

To cancel a job:

1. Open **Jobs**.

Click the **Menu** button (on the ribbon), select *Manage* and then click **Jobs**.

The *Job Management* dialog appears.

2. Select the job in the list you want to cancel.

Note: You can only cancel one job at a time.

3. Click **Cancel**.

After the operation is processed, the **Canceled** status appears.

Checking the status of a job

Blueprint provides you with the ability to check the status of any jobs you have started. Instance administrators with the [correct privileges](#) can view the details of any job within the instance.

To check the status of a job:

1. Open **Jobs**.

Click the **Menu** button (on the ribbon), select *Manage* and then click **Jobs**.

The *Job Management* dialog appears.

2. Select the job in the list you want to view.

The job details appear in the *Details* pane.

About notifications


After you start a job, the job runs in the background and Blueprint notifies you whenever the job status changes. There is no need to manually keep track of your job status or to wait while a progress bar finishes.

A notification (🚩) appears in the status bar whenever a job status changes to any of the following:

- Running
- Completed
- Terminated
- Failed

When a job has completed, the *Completed* job status contains a link to the result, which differs according to job type. A completed document generation job links to a document artifact whereas an ALM export links to the next required job.

The following image shows an example of a document generation job that has completed. The **Status** links to the resulting output, a document artifact.



Whereas document generation only consists of completing a single job, exporting artifacts to an ALM target consists of completing two jobs (a change summary and an export). For more information on document generation and exporting artifacts to an ALM target, see [Generating an office document](#) and [Exporting artifacts to an ALM Target](#).

When a job has terminated or failed, you have the option of restarting the job in the *Job Management* dialog. For more information on restarting jobs, see [About job management](#).

To open a notification:

- Click the **notification** icon (🚩) that appears in the bottom leftmost part of the application window.

The *notification* dialog appears.

If a *Completed* job status appears, click the link to see the job result or to open the next job.

About saving artifacts as images

Blueprint allows you to save visual artifacts, such as diagrams, as an image file on your computer so you can use it for other purposes. For example, you may want to print the image or e-mail it to others.



Tip: If you want to share the artifact with others, you may want to consider [sharing the artifact with Blueprint](#) instead of distributing an image. If you share the artifact using Blueprint, the viewers can see all associated information about the artifact such as properties and comments.

When you save an artifact as an image, Blueprint always creates an image using the settings that are currently in use. The zoom level is the only exception to this rule. For example, if you have grid lines enabled in Blueprint when you save the image, the grid lines are included in the image. The image is always saved with a 100% zoom level, regardless of the current setting in the artifact editor.

Applicability

You can save the following artifacts as an image:

- Use case (*workflow view* only)
- Use case diagram
- Business process diagram
- Generic diagram
- Domain diagram
- UI mockup
- Storyboard

When the *Save to Image* feature is applicable, a **Save to Image**  button appears on artifact editor contextual tab on the ribbon. For example, if you open a generic diagram, the **Save to Image**  button appears on the ribbon (*Generic Diagram* tab, *Image* group). If you open an actor or document artifact, this button is not available.

Supported image formats

You can save diagrams to the following image formats:

- PNG
- JPG

Saving an artifact as an image

To save an artifact as an image:

1. Open the artifact that you want to save as an image.

The *Save to Image* feature is only available for visual artifacts (such as diagrams). Refer to the [Applicability](#) section to learn more about support for this feature.

2. Click the **Save to Image**  button on the ribbon.

The **Save to Image** button is located on artifact editor contextual tab (example: *Generic Diagram* tab) in the *Image* group.

3. Specify the location, file name, and file type.
4. Click **Save**.

You can now access the image on your computer at the location you specified.

About test generation


Test generation allows you to generate test plans from your use cases. You can also export the tests to an ALM target.

Blueprint generates a test for each path variation that can be taken in a use case. For example, if you have a simple use case with one alternate flow, there are 2 possible paths that can be taken. Therefore, Blueprint generates 2 tests for this use case. One of the tests would cover the main flow of the use case, and the second test would take the alternate flow.

Follow the example below to learn more about how test generation works in Blueprint.

Example

Here's the simple use case that we will use to generate a test plan:



A test plan was generated with the following options:

- **Selected use case only:** there are no included use cases in the example, so this option is satisfactory.
 - Generate only for **10** levels: the test plan will generate tests for level 10 and below (that is, all use case levels).
- **Break loop-backs:** Yes















Here's the an example of the generated test plan in **.csv** format:

	A	B	C	D	E
1	Test Generation Parameters:				
2					
3	Revision: Live				
4	Top Use Case: UC588369: Login				
5	Use Case Only? Yes				
6	Break loop-backs? Yes				
7	Timestamp: 15/03/2012 3:26:02 PM				
8					
9	Test Generation Results:				
10					
11	# of Tests: 2				
12	# of Execution Paths: 1				
13	Pre-Condition (for all tests): User wants to login				
14	Post-Condition (for all tests): User is authenticated and can access other parts of the system				
15					
16	Execution path: UC588369				
17	# of Tests: 2				
18					
19	Test 1				
20	STEP #	INPUT	REFERENCES	EXPECTED RESULT	REFERENCES
21		1 Employee navigates to the login screen.		System displays login screen.	
22		2 Employee enters username and password, and clicks Login.		System authenticates and displays the Main Screen.	
23					
24	Test 2				
25	STEP #	INPUT	REFERENCES	EXPECTED RESULT	REFERENCES
26		1 Employee navigates to the login screen.		System displays login screen.	
27		2 Employee enters username and password, and clicks Login.		System displays a Login Error message.	
28					

Because the example only contains one alternate flow, there are 2 path variations in this use case. Therefore, there are a total of 2 tests generated for this use case. There are a number of columns that provide you with data:

- **INPUT:** provides the actor steps
- **EXPECTED RESULT:** provides the system steps
- **REFERENCES:** provides information about any included use cases, external flows, attached UI Mockups, and so on.

Here's an example of the one of the tests after exporting to HP ALM:

Details		Design Steps	Test Script	Test Parameters	Attachments	Req Coverage	Linked Defects	Dependencies	History
             									
Step ID	Step Name	Description	Expected Result						
1	Test Step 1	Employee navigates to the login screen.	System displays login screen.						
2	Test Step 2	Employee enters username and password, and clicks Login.	System authenticates and displays the Main Screen.						

Generating a test plan

When you generate a test plan, you can view the generated tests in **.csv** format. You can also export the tests to an ALM system if your project administrator has configured an ALM target and granted you access to it.

To generate a test plan from one or more use cases:



1. Click the **Test Plans** button on the ribbon (*Import/Export* tab, *Export* group).
The *Select Project* screen of the *Test Plan Generation* dialog is displayed.
2. Select the project that contains the use cases that you want to generate tests for, and then click **Next**.
The *Select Revision* screen appears.
3. Select whether you want to generate tests from data in live artifacts, or data from a baseline or review, and then click **Next**.
The *Select Use Cases* screen appears.
4. Place a check mark beside all use cases that you want to generate tests for, and configure the use case options if required.
The following options are available:

- **Selected use case only** (default): If this option is chosen, only the selected use cases are included in the test plan.
 - **Selected use case and children**: If this option is chosen, the test plan also generates tests for all included use cases and external flow use cases.
 - Generate only for **10** (default) levels: Defines the number of levels to include in the tests.
 - **Break loop-backs**: If selected, loop-backs are broken in order to reduce the number of tests in the test plan. The resulting test plan still provides full test coverage but does not cover all permutations of conditions.
5. Click **Next** to generate the tests.
- Please wait while the test plan is generated. The *Review Test Plans* screen is displayed after the test generation is complete.
6. Click **Download tests to CSV** to save the tests as a **.csv** file.

Note: If you are using Internet Explorer 8, you must enable the *automatic prompting for file downloads* security setting before you can download the file from Blueprint. To enable this setting, click **Tools > Internet Options > Security > Custom level... > Downloads** and then enable the **Automatic prompting for file downloads** option.

You can open this file in Microsoft Excel to review the test plan.

7. Click **Next** or **Finish**.
- The **Next** button is only available if your project contains [ALM targets](#). If your project contains ALM Targets, you can click **Next** to export the tests to your ALM Target.
8. On the *Select Target* screen, select the target that you want to export the tests to, and then click **Finish**. Or, click the **Cancel** button to close the dialog without exporting the tests to an [ALM target](#).

Social collaboration


Blueprint offers a variety of features that facilitate collaboration in Blueprint:

- [Activity center](#)
- E-mail notifications
- [Commenting](#)
- [Sharing artifacts](#)

About the activity center

The *activity center* is a powerful feature that keeps you up-to-date about artifacts that you care about. It also provides easy access to all reviews in which you are a participant.

You can access the activity center by clicking **Activity Center** in the explorer panel. The activity center appears in the main content area. It displays recent activities on the left side, and on the right side it provides a list of all the reviews to which you are a participant. The activity center looks like this:



Recent activities provide an overview of what is happening with artifacts that you care about in all of your projects, not just the projects that you currently have opened. Blueprint displays up to 60 of the most recent activities.

Populating your activity center

There are two ways to start populating your activity feed:

- Follow an artifact

Following an artifact in Blueprint is similar to following a person in other social media applications. When you follow a Blueprint artifact, the activity center is populated with activities whenever users edit, delete, or comment on that artifact. To follow an artifact, simply select the artifact and click the **Follow** button in the artifact header.

You can follow an artifact in two ways:







- Manually follow an artifact by clicking the Follow button.
- Automatically follow an artifact:
 - when you create a new artifact (authors automatically follow the artifacts they create).
 - when you comment on an artifact.

- when you are mentioned in a comment by another user.
- Participate in a review


When the review has been started or closed, your activity center is updated with a new activity.

Understanding the items that appear in your activity center

The following table outlines the activities that can appear in your activity center:

Activity Type	This activity occurs <u>when</u> ...	This activity occurs <u>because</u> ...
	A new version of an artifact has been published.	You are following the artifact with the newly published version.
	An artifact has been deleted.	You are following the artifact that has been deleted.
	A comment has been added to, or deleted from, an artifact.	You are following the artifact with the added or deleted comment.
	You have been added to a review.	You are a participant in the review.
	You have been removed from an review.	You were previously a participant in the review.
	The review status has changed to active or closed.	You are a participant in the review.

Removing items from your activity center

The *actions*  button appears beside every activity in the activity center. This is the button you must use to remove activities from your activity center. You can remove activities one at a time, or you can remove all review activities (for a particular review) at once.

From the *actions* menu, you can also click the **Unfollow Artifact** option to prevent future activities from appearing for that particular artifact.

Note: When you remove items, the action is cached. If you login to Blueprint using a different browser or on a different computer, the activities will reappear.

To remove activities from your activity center:


1. Click the *actions*  button located beside an activity.



2. Select **Remove this Activity**.

To remove all review activities (for a particular review) from your activity center:

1. Click the *actions* ⚙ button located beside a review activity.



2. Select **Remove All Activities for this Review**.

About discussions and commenting


Comments allow multiple stakeholders to collaborate on requirements. Blueprint users or e-mail collaborators can add comments to any artifact or sub-artifact, including (but not limited to) textual requirements, use cases, actors, use case steps, diagrams, shapes in diagrams, glossaries, and glossary terms.

You may also be interested in learning how you can use the [activity center](#) to stay up-to-date about what's going on in your projects.


The *Discussions* tab allows you to view comments, create new comments, reply to existing comments, and change the status of discussions.

Note: Comments and replies cannot be deleted, unless your project administrator has enabled this feature. You can collapse a discussion and change the status to *closed*.

The *Discussions* tab in the utility panel looks like this:



A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:




Determining whether or not an artifact contains open discussions

When an artifact contains comments, the *discussion* 💬 indicator is displayed in a column in the artifact list. Click the **Column Options** button on the ribbon (*View tab, Artifact List group*) to enable the display of this column.

If you uncheck the **Discussions** option on the ribbon (*View tab, Show Indicators group*), the *discussion* indicator is also displayed in the upper right corner of each sub-artifact (example: shape) that contains open discussions.

Example






Viewing comments in the utility panel

You can view comments for any artifact or sub-artifact by performing the following steps:

1. Open or select the artifact that contains the comments you want to view.
Click the artifact ID link of the artifact you want to open.
To view comments for sub-artifacts, select the sub-artifact (example: click a shape in a diagram).
2. Open the *Discussions* tab in the utility panel.

1. Click the *Discussions* tab  icon.


You can also point to the tab icon to view the name of the tab.

Discussions can be expanded and collapsed by clicking anywhere on the header of the discussion, or by using the expand  and collapse  buttons. When you click the collapse  buttons, the entire discussion is collapsed, including the original comment and all replies.

You can change the status of a discussion to either *Open* or *Closed*. The status is applied to the entire discussion. In other words, you cannot assign a status to individual comments and replies. Read more about [changing the status of a discussion](#).

Note: Your project administrators may have configured custom discussion status values in addition to the default status values of *Open* and *Closed*.

A discussion looks like this:




Adding a new comment

Comments allow multiple stakeholders to collaborate on requirements. Blueprint users or e-mail collaborators can add comments to any artifact or sub-artifact, including (but not limited to) textual requirements, use cases, actors, use case steps, diagrams, shapes in diagrams, glossaries, and glossary terms.

Note: Comments and replies cannot be deleted, unless your project administrator has enabled this feature. You can collapse a discussion and change the status to *closed*.

To add a new comment to an artifact:

1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *Discussions* tab in the utility panel.
 1. Click the *Discussions* tab  icon.
You can also point to the tab icon to view the name of the tab.
3. Click the New Comment link.
A new text field appears.
4. Type your comment into the space provided.
5. Click the **Publish** link located below the comment to publish it.

Note: You must publish your comments, or publish the artifact, before you comments can be viewed by other users.

Mentioning someone in a comment

Overview

Note: To use this feature, [e-mail integration settings](#) must be enabled and configured by your instance administrator.

Within comments you have the ability to mention other Blueprint users as well as stakeholders that do not use Blueprint. Comments allow multiple stakeholders to collaborate on requirements. Blueprint users or e-mail collaborators can add comments to any artifact or sub-artifact, including (but not limited to) textual requirements, use cases, actors, use case steps, diagrams, shapes in diagrams, glossaries, and glossary terms.

Note: Comments and replies cannot be deleted, unless your project administrator has enabled this feature. You can collapse a discussion and change the status to *closed*.

To mention a user in a comment:

1. Type the @ symbol and attach the name of the user or e-mail address of the person you want to mention.
Example: **@David** or **david@acme.com**

If you are mentioning a Blueprint user or an e-mail address that has been referenced in a comment before, Blueprint displays a list of matching users and e-mail addresses.
2. Click the user or e-mail address that you want to mention in your comment.
 - If you are entering an e-mail address that has not been mentioned before, press ENTER.


After you publish the comment, the individual that you mentioned receives an e-mail notification if your instance administrator and project administrator have configured and enabled e-mail notifications from the [Instance Administration Console](#) and Project Administration Console. Also, if you mentioned a Blueprint user, the user is now automatically following the artifact. By following the artifact, the user will receive updates about the artifact in the Activity Center.

Replying to an existing comment

Comments allow multiple stakeholders to collaborate on requirements. Blueprint users or e-mail collaborators can add comments to any artifact or sub-artifact, including (but not limited to) textual requirements, use cases, actors, use case steps, diagrams, shapes in diagrams, glossaries, and glossary terms.

Note: Comments and replies cannot be deleted, unless your project administrator has enabled this feature. You can collapse a discussion and change the status to *closed*.

To reply to an existing comment:

1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *Discussions* tab in the utility panel.
 1. Click the *Discussions* tab  icon.
You can also point to the tab icon to view the name of the tab.
3. Click the Reply link.
A new text field appears.
4. Type your comment into the space provided.
5. Click outside of the field to exit edit mode.

Note: You must publish your comments, or publish the artifact, before you comments can be viewed by other users.

Changing the status of a discussion

There are two default discussion status values: *Open* and *Closed*. The discussion status can be helpful for keeping track of which comments have already been addressed. For example, if a stakeholder's feedback has already been addressed, the discussion can be set to *Closed*.

Note: Your project administrators may have configured custom discussion status values in addition to the default status values of *Open* and *Closed*.

To change the status of a discussion:

1. Click the discussion status.

The following drop-down menu appears:




2. Select a status for the discussion.

Use the drop-down option to select *Open* or *Closed*.

Note: Your project administrators may have configured custom discussion status values in addition to the default status values of *Open* and *Closed*.

About artifact sharing

There are few different ways to share artifacts:

- Via e-mail
- Via a hyperlink (that can be included in an instant message or e-mail)
- Mention another user in a comment so the user receives an email notification
- [Using the share icon](#) () at the top of the open artifact (*main content area*)

Note: Only project administrators with the [correct permissions](#) can perform this action.

Sharing artifacts from the utility panel browse tab

Sharing artifacts allows you to easily direct other individuals to the artifact. Artifacts are shared using hyperlinks.

When you share a folder, the hyperlink contains an associated view. When another user opens the hyperlink, the associated view is identical to your view of the artifact list at the time that you shared the folder.

You can share an artifact link via e-mail, or you can copy the link to the Clipboard and paste it into other applications such as instant messaging.

To share an artifact (via e-mail):

1. Open the *browse* tab in the utility panel.

Click the *browse*  tab.

You can also point to the tab icon to view the name of the tab.

2. Right-click the artifact that you want to open.

The context menu appears.

3. Click **Share > Via e-mail**.

A new email message is initiated in your default email program. The email message contains a link to the artifact.

To share an artifact (via Clipboard):

1. Open the *browse* tab in the utility panel.

Click the *browse*  tab.

You can also point to the tab icon to view the name of the tab.

2. Right-click the artifact that you want to share.

The context menu appears.

3. Click **Share > Copy to Clipboard**.


A link to the artifact is copied to the Clipboard so you can paste it into another application, such as email or instant messaging.

Artifact versioning and history

Artifact history refers to the ability to view historical versions of an artifact. Every time you publish an artifact, a new version is saved and can be viewed at any time by opening the History ☺ tab in the utility panel.


The *history* tab allows you to view previous versions of the artifact and compare changes between them.

The *history* tab in the utility panel looks like this:



Version	Author	Date
3	Christina McNish	4/4/2013 10:19 AM
2	Christina McNish	2/27/2013 10:56 AM
1	Christina McNish	2/21/2013 9:19 AM

A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:



Name	Id	Type	Width	Height
Online Banking System...	GD4668410	Generic Diagram	1308	768

Understanding the utility panel history tab

The *history* tab displays a history table with the following columns:

- **Version:** Indicates the version number.

Note: Version 1 is always the first version of the artifact. The highest version number is always the *most recent*. However, keep in mind that you, or another user, may have made changes to the *most recent* version and not yet published the changes. In this case, a new version appears in the history table after the changes are published.

- **Author:** Indicates the name of the person who published the version.
- **Date:** Indicates the date and time the version was published.

Sorting and filtering historical versions


Sorting versions


You can sort the historical versions by version number, author or date. Simply click the column headers to toggle between an ascending or descending sort order.

Filtering versions

You can filter versions by version, author and date. Sorting can be useful in many cases but sometimes there may be an extremely large number of versions. In this case, it may be more effective to filter versions rather than sort them.

To apply a filter:

1. Click the filter  button located beside the column header text, depending on the type of filter you want to apply.
2. Specify your filter criteria. Refer to the sections below for more information about filtering by version number, author and date.
3. Click the **Filter** button.


After applying a column filter, the filter icon changes to yellow . The yellow filter icon is a visual reminder that the filter is applied.

To remove a filter:

1. Click the **Clear Filter** button located on each of the filter dialogs.

FILTERING BY VERSION NUMBER

Filtering by version allows you to filter the versions based on the version number. The *version filter* dialog looks like this:



You can filter by version using one of three methods:


- Place a checkmark beside the versions you want to display.

- Build a query using the operator drop-downs and by specifying appropriate values. For example, you can *Show rows with value that is less than or equal to 100 And is greater than or equal to 90*. This query will return versions 90 to 100 inclusive.
- A combination of the previous two methods. If you select versions using the check boxes *AND* by specifying query values, versions are only displayed in the results if all criteria is met.

FILTERING BY AUTHOR

Filtering by author allows you to filter the versions based on the name of the person who published the version.

The *author filter* dialog looks like this:


The screenshot shows a dialog box titled "Select All" with a close button (X). Inside, there is a list box containing the name "Steph Hubert". Below the list box is a text input field with the text "Show rows with value that contains" and a small "aA" icon to its right. At the bottom of the dialog are two buttons: "Filter" and "Clear Filter".

You can filter by version using one of three methods:

- Place a checkmark beside the publisher of the versions you want to display.
- Type the name (or part of the name) of the publisher of the versions you want to display. For example, type Fred to display all versions published by individuals with the name Fred or Freddy.
- A combination of the previous two methods. If you select versions using the check boxes *AND* by specifying query values, versions are only displayed in the results if all criteria is met.

FILTERING BY DATE

Filtering by date allows you to filter the versions based on the date the version was published. The *date filter* dialog looks like this:

The screenshot shows a dialog box titled "Select All" with a close button (X). Inside, there is a list box containing several dates and times: "10/17/2011 10:22:27 AM", "10/18/2011 2:32:16 PM", "11/24/2011 3:37:31 PM", "11/24/2011 3:37:37 PM", "11/24/2011 3:37:46 PM", and "11/24/2011 3:38:01 PM". Below the list box is a text input field with the text "Show rows with value that" and a dropdown menu. The dropdown menu is currently set to "is equal to". Below the dropdown menu is a text input field labeled "EnterDate" with a calendar icon to its right. Below the "EnterDate" field is another dropdown menu set to "And". Below the "And" dropdown menu is another dropdown menu set to "is equal to". Below the second "is equal to" dropdown menu is another text input field labeled "EnterDate" with a calendar icon to its right. At the bottom of the dialog are two buttons: "Filter" and "Clear Filter".


You can filter by version using one of three methods:

- Place a checkmark beside the publication date of the versions you want to display.
- Build a query using the operator drop-downs and by specifying dates. For example, you can *Show rows with value that is greater than 10/16/2011 And is less than 10/19/2011*. This query will return versions that were published on 10/17/2011 and 10/18/2011.
- A combination of the previous two methods. If you select versions using the check boxes *AND* by specifying query values, versions are only displayed in the results if all criteria is met.

Viewing a historical version of an artifact

Note: Historical versions of artifacts are read-only and cannot be modified.

To view the historical version of an artifact:


1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *history* tab in the utility panel.
 1. Click the *history* tab  icon.
You can also point to the tab icon to view the name of the tab.
3. Click the version ID link of the version you want to view.

The selected version is displayed in a new tab in the *main content area*.

Viewing the changes between two historical versions

You can view the changes between any two versions of an artifact. Viewing the changes between two versions can be beneficial if you have reviewed a version of the artifact, and then you want to determine what is different in the next version.


To view the changes between two historical versions:

1. Open an artifact.
Click the artifact ID link of the artifact you want to open.
2. Open the *history* tab in the utility panel.
 1. Click the *history* tab  icon.
You can also point to the tab icon to view the name of the tab.
3. Select the versions to compare.
You can select a version by clicking a row in the table. Any selected rows are highlighted in blue. To select multiple rows, simply hold the **Ctrl** key and click a second row.
 - If you select only one version, the version will automatically be compared to the previous version.
 - If you select two versions, the two selected versions are compared.

The changes are automatically displayed at the bottom of the *history* tab in the utility panel.

Understanding the changes

Changes between versions are displayed at the bottom of the *history* tab in the utility panel as soon as a version is selected. The summary of changes looks like this:



The change history panel is labeled with the artifact name, and outlines the two versions that are compared (example: *New Generic Diagram 1, V2 and V3*).

When changes to properties have occurred, you can click the arrow that appears next to **Properties** and view the additional details about the changes.


Note: Blueprint displays **No History Available** if you have only selected Version 1, because there is no previous version for comparison. The **No History Available** message is also displayed if you select more than two versions, because you cannot compare more than two versions.

To view a specific version of an artifact, click the version number in the **Version** column. The selected version of the artifact appears in the main content area.

Viewing the changes between two versions of an artifact using Side by Side

You can view the changes that have occurred within any artifact by using *Side by Side View*.

Here's an example of two different versions of a UI mockup being compared in *Side by Side View*:



To view the changes between two versions of an artifact:

1. Select the artifact you want to view.
2. Select the two versions you want to compare (*History* tab, Utility Panel).
To select two different versions of an artifact, press CTRL and then select the artifacts.
3. Click the **Open Side by Side View** link (*History* tab, Utility Panel).

The two versions appear in a new tab.

To open the latest version of the artifact, click the **Open Latest Version** link.

About Version Compare

Overview

Version Compare provides you with the ability to look at the changes that have been applied to an artifact over a selected period of time. Version Compare works with all types of artifacts in Blueprint.

Example

Susan, a business analyst, wants to see what has changed between major milestones in her project so she compares two different baselines.

Example

Latoya, a business analyst, has received approval on a formal review that she sent out a couple of weeks ago. Since then, some additional feedback has come in and some additional changes have been made to the artifacts. Latoya wants to see all of the changes that need to get re-approved so she compares the review to a live timestamp.

Example

Maria, a business analyst, created an artifact and then shared the artifact with stakeholders. Over time, multiple stakeholders made many changes to the artifact. Maria wants to see what changes were made, when and by whom, so she compares the artifact to a past timestamp.

At a high level, Version Compare is a three step process:

1. Select a project node, a folder or artifact(s).
2. Click the **Version Compare** button.
3. In the *Version Compare* dialog, select a baseline, review or timestamp.

When the Version Compare report is generated, the report displays changes between the items you selected in Step 1 and the items or timestamp that you selected in Step 3.

You can compare the following:

■ Baseline

After you select a baseline and open the Version Compare dialog, you can compare the baseline to the following:

- The contents of another baseline.
- The contents of a review.
- Timestamp (that is, the baseline at a particular point in time).

■ Review

After you select a review and open the Version Compare dialog, you can compare the review to the following:

- The contents of a baseline.
- The contents of another review.
- Timestamp (that is, the review at a particular point in time)

■ Project node

After you select a project node and open the Version Compare dialog, you can compare the project node to the following:

- The contents of a baseline.
- The contents of a review.
- Timestamp (that is, the project node at a particular point in time).

■ Artifact(s)

After you select one or more artifacts and open the Version Compare dialog, you can compare the artifact (s) to the following:

- The contents of a baseline.
- The contents of a review.
- Timestamp (that is, the artifact(s) at a particular point in time).

■ Folder(s)


After you select one or more folders and open the Version Compare dialog, you can compare the folder(s) to the following:

- The contents of a baseline.
- The contents of a review.
- Timestamp (that is, the folder(s) at a particular point in time).

Version Compare report

A Version Compare report provides you with the ability to view changes that have occurred within an artifact, a set of artifacts, a baseline or a review over a selected period of time. Version Compare provides a list of actions that have occurred over the selected period of time. The Version Compare report always compares changes from the older date to the newer date.

Tip: You can sort and filter your Version Compare results the same way you would sort or filter any artifact list in Blueprint. You can also [export your Version Compare report to Excel](#).



The screenshot shows a 'Version Compare' window for project 'PR1208368: BP Air...'. It compares the current version (April 20th) with a previous version (July-25-13 12:00 AM). The table below lists the changes:

Action	Name	ID	Artifact Type	Change Type	Change Summary	Last Edited By	Last Edited Date
Created	Mobile Support	FR5804420	Functional Requirement	Artifact Created		Allison Burnett	26/07/2013 3:46 PM
Modified	Scope Summary	BR1208375	Business Requirement	Property Changed	Priority	Allison Burnett	26/07/2013 3:46 PM
Modified	Book a Flight	UM1208494	UI Mockup	Sub-Artifact(s) Changed		Allison Burnett	26/07/2013 3:58 PM
Modified	Scope Summary	BR1208375	Business Requirement	Property Changed	Risk_1	Allison Burnett	26/07/2013 3:59 PM
Modified	Online Reservations	BR1208376	Business Requirement	Property Changed	Status_1	Allison Burnett	26/07/2013 3:59 PM
Modified	Online Check-in	BR1208378	Business Requirement	Property Changed	Description	Allison Burnett	26/07/2013 3:59 PM
Modified	Create Online Account...	UR1208400	User Requirement	Property Changed	Name	Allison Burnett	26/07/2013 4:00 PM
Modified	Online Check-in	BR1208378	Business Requirement	Property Changed	Version	Allison Burnett	26/07/2013 4:01 PM
Deleted	International Flights	UR1208412	User Requirement	Artifact Deleted		Allison Burnett	26/07/2013 4:09 PM
Modified	International Restrictions	RU1208387	Business Rule	Relationship Removed		Allison Burnett	26/07/2013 4:09 PM
Modified	Modify a Flight	UR1208392	User Requirement	Relationship Changed		Allison Burnett	26/07/2013 4:12 PM
Modified	Modify an Existing Flight	FR1208421	Functional Requirement	Relationship Changed		Allison Burnett	26/07/2013 4:12 PM

Here's an explanation of the data contained in each Version Compare report, outlined in the order the columns appear:

Data Field	Description
Action	The type of action that the user applied to the artifact.
Name	The name of the artifact that was affected.
ID	The ID of the artifact that was affected. The ID contains a hyperlink to the artifact.
Artifact Type	The type of artifact that the action was applied to.
Change Type	The part of the artifact that changed. For example: a relationship, sub-artifact or actor inheritance might have changed within the artifact.
Change Summary	Identifies the name of the item that changed. For example: the Description of the artifact might have changed.
Last Edited By	The user that last performed the action.
Last Edited Date	The time and date the last action occurred.

Different ways of accessing Version Compare

You can access Version Compare in any of the following ways:

- Right-click an artifact and then click **Version Compare**
- Select an artifact and then click the **Version Compare** button on the ribbon (*Home* tab, *Artifacts* group)
- Right-click a folder or project node in the *Explorer* panel and then click **Version Compare**
- Open the contents in a baseline and then click the **Version Compare** button on the ribbon (*Home* tab, *Artifacts* group)

Comparing versions of an artifact

You can view the changes that have occurred within an artifact, multiple artifacts, a review or a baseline by using Version Compare.

To compare versions of an artifact:

Note: Before using Version Compare, make sure to save and/or publish the artifacts you want to compare.

1. Select a project node, a folder, a baseline, a review or artifact(s) that you want to compare.

Note: Regardless of whether you selected the newest or oldest version(s) of your artifact(s), review or baseline, Blueprint always compares the oldest contents in the Version Compare analysis to the newest contents.

2. Click the **Version Compare** button on the ribbon (*Home* tab, *Artifacts* group).

The *Version Compare* dialog box appears.

If you want to include all children in your Version Compare report, select the **Compare all children of the selected artifact(s) to the baseline, review package or timestamp selected above** check box.

3. Select a baseline, review package or a timestamp to compare your contents with.
4. Click **OK**.

Your Version Compare report opens in a new tab. Each action applied to your artifact appears on a new line and the artifact data is organized according to columns. To learn more about Version Compare reports, see [Version Compare report](#).

Exporting a Version Compare report to Excel

Blueprint allows you to export your Version Compare report to Microsoft Excel. Once exported, you can use Microsoft Excel to print your report.

To export your Version Compare report to an Excel document:

1. Click the **Artifact List View** button on the ribbon (*Import/Export* tab, *Export* group).
The *Save As* dialog box appears.
2. Name the file with an *.xls* extension in your preferred location and then click **Save**.
Your artifact appears in an Excel file.
In Excel, you can perform any stylistic edits and print the artifact with your preferred settings.
3. Print your Version Compare report.
On the **File** menu, click **Print**.
Click the **Print** button.
When the print dialog box appears, click **OK**.

About Baselines

A *baseline* artifact is a snapshot in time of one or more artifacts in a project. Baselines provide you with a reference point for viewing project artifacts as they existed at a particular point in time, even after the artifacts have changed. Baseline artifacts can be included in reviews to obtain feedback and approval.


Baselines can be sealed or unsealed:

- A *sealed baseline* contains a timestamp and contents that can no longer be modified. Sealing a baseline is a manual action performed by a user and once sealed, a baseline can never be unsealed. Only artifacts in sealed baselines can be Approved as part of a review.
- When a baseline is *unsealed*, you are able to modify the contents. While artifacts in an *unsealed* baseline can be viewed and commented on as part of a review, they cannot be Approved.

Finding your baseline artifacts

Baseline artifacts are special artifacts that are treated somewhat differently than other artifacts in Blueprint. Baseline artifacts are stored in a separate location in Blueprint.

You can find your project's baseline and review artifacts by clicking the **Baselines and Reviews** folder located below your project in the *explorer* panel of Blueprint:



Typical Baseline Usage

Baselines are typically created as you reach a milestone in the project. Baselines ensure that you can view the artifacts as they existed at a particular moment in time.

If you need a record of artifacts at a particular moment in time (for any reason):

1. [Create a new baseline artifact.](#)
2. [Configure and seal the baseline artifact.](#)
3. If artifacts are ready to be reviewed and approved, you can [add a review](#) and [configure the review](#) to include the baseline in the review contents.

Baseline Artifact Properties

By default, a baseline artifact contains the following system properties:

- **Name:** Indicates the name of the **baseline**.
- **Id:** Provides a unique identifier for the **baseline**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **Sealed:** Indicates whether or not the artifact is sealed. This property can be *Yes* or *No*. When a baseline artifact is sealed, you can no longer change the baseline contents.
- **Description:** Provides a description of the **baseline**.

Your instance administrator can configure standard properties for each standard artifact type.


Creating a new baseline



A *baseline* artifact is a snapshot in time of one or more artifacts in a project. Baselines provide you with a reference point for viewing project artifacts as they existed at a particular point in time, even after the artifacts have changed. Baseline artifacts can be included in reviews to obtain feedback and approval.

You can create a baseline within the *Baselines and Reviews* folder or you can add artifacts to a new baseline within the artifact list. For more information on the latter topic, see [Adding an artifact to a baseline](#).

To add a baseline artifact:

1. Click the **Baselines and Reviews** folder in the explorer panel.



2. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
3. Select **Child Artifact**.
4. Click the baseline  icon.

Next, you will probably want to configure and seal the baseline. Read more about [Configuring and sealing a baseline](#)

Configuring and sealing a baseline

After you have [created a new baseline](#) or [added artifacts to a baseline](#), you must configure a few settings before you can seal the baseline.

Baselines can be sealed or unsealed:


- A *sealed baseline* contains a timestamp and contents that can no longer be modified. Sealing a baseline is a manual action performed by a user and once sealed, a baseline can never be unsealed. Only artifacts in sealed baselines can be Approved as part of a review.
- When a baseline is *unsealed*, you are able to modify the contents. While artifacts in an *unsealed* baseline can be viewed and commented on as part of a review, they cannot be Approved.

To configure and seal a baseline:

1. Provide a name for the baseline artifact.
Type a name into the `Name` field.

Tip: We recommend that you choose a name that is descriptive, but relatively short in length.

2. Set the baseline timestamp.

1. Click the *calendar* button  and select the desired date and time, or click the **Live** button to reference the live versions of the artifacts.

Note:

After you save the baseline artifact with a time stamp, the baseline will reference the artifacts as they existed at that particular day and time.

If the `Timestamp` is set to *Live Artifacts*, the baseline contents will always reference the most up-to-date (live) versions, until the baseline is sealed. If the `Timestamp` is set to *Live Artifacts* when you seal the baseline, the `Timestamp` is automatically updated with the current date and time, and the baseline will always reference the versions as they existed at that date and time.

2. Click **Close** to close the calendar.

3. Provide a description for the baseline.

1. Type a description into the `Description` field.

The description can be used for any purpose, but it is typically used to provide information about the purpose of the artifact.

4. Choose the artifacts to include in the baseline.

1. Click the **Select Baseline Content** button. The *Select Baseline Content* dialog appears. By default, all artifacts are added to the *Baseline Contents* section on the right side of the dialog.
2. Use the **Add** and **Remove** buttons to move all of the desired artifacts to the right side of the dialog.
3. Click **OK** to save the baseline contents.

Note: If any of the selected artifacts are currently being edited, a warning is displayed. The options are **Continue**, **OK**, or **Cancel**. Click the **Continue** button to select the content with the unsaved versions of the artifact. Click the **OK** button to close the dialog. Click the **Cancel** button to completely cancel the content selection.

5. Seal the baseline.

1. Click the **Seal Baseline** button to seal the baseline.

Viewing baseline contents


The purpose of creating a baseline is to gain the ability to view artifacts as they existed a particular moment in time.

Note: Baseline contents are read-only and cannot be modified.

To view baseline contents:

1. Click the **Baselines and Reviews** folder in the explorer panel.

You can find your project's baseline and review artifacts by clicking the **Baselines and Reviews** folder located below your project in the *explorer* panel of Blueprint:



2. Open the baseline artifact that contains the baseline contents that you want to view.

The baseline contents appear in the main content area.

Deleting a baseline

Note: You cannot delete baseline artifacts that are sealed.

Tip: Consider creating folders to organize your baseline artifacts. For example, you may want to create a folder named **Archive** to store the artifacts that you used for testing, or those that you no longer need.

To delete a baseline:

1. Open the **baseline** that you want to delete, or select the **baseline** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.


After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.


Click **Yes** to confirm deletion, or click **No** to cancel.

Adding an artifact to a baseline

Blueprint allows you to conveniently add one or more artifacts to a baseline without leaving your artifact list.



You can also create a new baseline for your selected artifact within the same operation.




Alternatively, you can create a baseline from within the *Baselines and Reviews* folder (*Explorer Panel*). For more information about creating a baseline, see [Creating a new baseline](#).

Adding an artifact to a baseline

To add an artifact to a baseline:

1. Select the artifacts in your artifact list that you want to add to a baseline.
You can also add a single artifact to a baseline when the artifact editor is open.
2. Click the *Add To* button on the ribbon and then click **Baseline** (*Home* tab, *Artifacts* group).



The *Add to Baseline(s)* dialog box appears.

Tip: To add all of the contents of any selected folder(s), select the **Add all children of the selected artifact(s) to the baseline(s)** check box.

3. Select your baseline(s) and then click **OK**.
To create a new baseline, click **Create Baseline**.

The baseline(s) appear(s) with your included artifacts.


Next, you will probably want to configure and seal the baseline. Read more about [Configuring and sealing a baseline](#)

Traceability and relationships


A *trace* is a type of relationship between two artifacts or sub-artifacts. Traces are used to establish and define the direction of a relationship. Blueprint allows you to create traces to/from any artifact or sub-artifact, with the exception baseline and review artifacts.

The *Relationships* tab in the utility panel allows you to view and add artifact traces, effectively establishing relationships with other artifacts.

The *Relationships* tab in the utility panel looks like this:




A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:



Trace Types



There are 3 types of traces, depending on the direction of the relationship between two artifacts.

Icon	Name	Description
←	<i>From</i> Trace	A <i>From</i> trace describes a one way relationship to an artifact From the artifact in the utility panel.
→	<i>To</i> Trace	A <i>To</i> trace describes a one way relationship from an artifact To the artifact in the utility panel.
↔	<i>Bidirectional</i> Trace	A <i>Bidirectional</i> trace indicates a two way relationship between an artifact and the artifact in the utility panel.

If a red exclamation point appears on the relationship indicator (example: ) , the trace relationship has been marked with the *suspect* flag. Read more about [Adding and removing the trace suspect flag](#).

Viewing and filtering relationships

To view the relationships of an artifact, simply open the *Relationships* tab in the utility panel. The relationships are displayed in a table. Example

	ID	Title	Project
^ Trace			
	GL4668408	Technical Terms	Online Banking
	FR4668420	Customer Accounts Screens	Online Banking

The table contains the following columns:

- The left most column indicates the type of trace. The trace type can be *From*, *To*, or *Bidirectional*.
- The second column indicates the type of artifact, by displaying the artifact icon.
- *ID*: The *ID* column indicates the unique ID of the artifact. You can click this link to open the traced artifact.
- *Title*: The *Title* column indicates the name of the artifact.
- *Project*: The *Project* column indicates the project the artifact belongs to.


To filter the information that appears in the *Relationships* tab, click the **Relationships** drop-down and select all of types of relationships you want to appear in the table:

- **Traces**: If selected, traces are displayed in the table.
- **Parent/Child**: If selected, parent and child artifacts are displayed in the table.
- **Other**: If selected, the following relationships are displayed:
 - Associations (see details)
 - UC Step to Actor
 - UC Step to UI Mockup
 - UC Step to Included UC
 - UC Step to External Alternate Flow
 - Inherited Actors
 - Document References

Adding traces from the relationships tab in the utility panel

Adding a trace establishes a relationship between two artifacts. Blueprint supports three different types of traces depending on the direction of the relationship. Read more about [Trace Types](#).

To add a trace using the *Relationships* tab in the utility panel:

1. Open the *Relationships* tab in the utility panel.
 1. Click the *Relationships*  tab .

You can also point to the tab icon to view the name of the tab.
2. Click the **Add Trace** link.

The *Traces* dialog appears.


Note: To trace an artifact across projects, you need *Trace* privileges for both projects and *Create and Edit* privileges for either project. Contact your Blueprint project administrator for more information about project role privileges.

3. Select the artifact that you want to trace and establish a relationship.

Search or browse of the appropriate artifact on the left side of the dialog.

4. Select the type of trace to create.

Click the drop-down arrow located on the right side of the **Trace** button, and select **To**, **From**, or **Bidirectional**.



Read more about [Trace Types](#).

5. Click the **Trace** button.

The new trace appears on the right side of the dialog.

6. Click **OK**.

The trace is saved and now appears in the traces table on the *Relationships* tab in the utility panel.

After the trace is saved, it appears on the *Relationships* tab in the utility panel. If you do not see the new trace, ensure that you have selected the **Traces** option in the **Filter** drop-down. Read more about [Viewing and filtering relationships](#).

Adding traces from the utility panel browse tab

A *trace* is a type of relationship between two artifacts or sub-artifacts. Traces are used to establish and define the direction of a relationship.

The utility panel provides you with the ability to quickly create a trace between an artifact in the *browse* tab to an artifact in the main content area or artifact list.

To add a trace from the browse tab in the utility panel:

1. Open the *browse* tab in the utility panel.

Click the *browse*  tab.

You can also point to the tab icon to view the name of the tab.

2. Drag and drop the artifact that you want to trace onto an artifact in the main content area or artifact list.

You can drag and drop any artifact or sub-artifact from the *browse* tab. You can drag and drop the artifact onto any artifact or sub-artifact in the main content area or artifact list.

After you drag the artifact, the trace menu appears.

3. Select the type of trace you want to add.

Select **Add Trace**, and then choose one of the following options:

- **To:** Creates a trace from the artifact in the *browse* tab *TO* the artifact in the *main content area*.
- **From:** Creates a trace to the artifact in the *browse* tab *FROM* the artifact in the *main content area*.

- **Bidirectional:** Creates a two way (bidirectional) trace.

Note: To trace an artifact across projects, you need *Trace* privileges for both projects and *Create and Edit* privileges for either project. Contact your Blueprint project administrator for more information about project role privileges.


Adding an inline trace

An *inline trace* creates a relationship between two artifacts and adds an inline hyperlink, allowing readers to click the link to open the traced artifact. In addition to the hyperlink creation, the traced artifact also appears in the *Relationships* tab in the utility panel.

You can add inline traces to any text field that supports [rich text formatting](#). The **Add InLine Trace** button is located on the ribbon (*Home* Tab, *Relationships* group) and is only accessible if you are editing a text field that supports rich text formatting.

To add an inline trace:

1. Place your cursor in a text field that supports rich text formatting.

If the text field does not support inline traces, the **Add InLine Trace** button is inaccessible  (that is, grayed out).

2. Click the drop-down arrow on the **Add InLine Trace** button.

The drop-down arrow on the **Add InLine Trace** button looks like this:



3. Select the type of trace you want to add.

Read more about [Trace Types](#) for more information.

4. Click the **Add InLine Trace** button.

The *Artifact Selection* dialog appears.

Note: To trace an artifact across projects, you need *Trace* privileges for both projects and *Create and Edit* privileges for either project. Contact your Blueprint project administrator for more information about project role privileges.


5. Select the artifact that you want to trace and establish a relationship.

Search or browse of the appropriate artifact on the left side of the dialog.

6. Click **OK**.

A new hyperlink is added to the text field.

Note: If an existing trace relationship already exists, Blueprint displays a dialog that asks you if you want to use the trace as it currently exists, or convert it to the selected trace type. [Example](#)






After you add the inline trace, the trace appears as a hyperlink in your text field. Example

When the user first visits the webpage, the login page [UC7664: Log in](#) must be displayed.

Changing the direction of a trace

You may need to change the direction of a trace if it was created incorrectly, or if a trace has changed from a one way relationship to a two way relationship, or vice versa. In other words, you can modify the trace direction without deleting and then re-creating the trace.

There are three trace direction types:

Icon	Name	Description
	<i>From</i> Trace	A <i>From</i> trace describes a one way relationship to an artifact From the artifact in the utility panel.
	<i>To</i> Trace	A <i>To</i> trace describes a one way relationship from an artifact To the artifact in the utility panel.
	<i>Bidirectional</i> Trace	A <i>Bidirectional</i> trace indicates a two way relationship between an artifact and the artifact in the utility panel.

You can view the direction of a trace by opening the *Relationships* tab in the utility panel. The first column of the table displays an *direction* icon for each trace.

To change the direction of a trace:

1. Open the *Relationships* tab in the utility panel.

1. Click the *Relationships*  tab .

You can also point to the tab icon to view the name of the tab.

2. Right-click the trace that has the incorrect direction.

The context menu appears.


3. Select **Change Direction** and then choose the direction you want.


A checkmark appears beside the trace direction that is currently selected.


After you change the trace direction, the icon is updated in the *traces* table (on the *Relationships* tab in the utility panel).

Adding and removing the trace suspect flag

When a trace is marked with a *suspect* flag, it generally indicates that one of the traced artifacts has changed, and as a result, the traced artifacts may require changes as well. Therefore, if you change an artifact, it is best practice to mark the traced artifacts as suspect so they can be reviewed and updated at a later time.

In the utility panel, traces that are marked with the suspect flag are displayed with a red exclamation point on the *relationship* indicator (example: ).

A red exclamation point is also displayed on the *relationship*  indicator if the artifact or sub-artifact contains at least one suspect trace. For example, if a shape (sub-artifact) contains at least one suspect trace, the *relationship* indicator is displayed with a red exclamation point in the diagram. Example



To add or remove the trace suspect flag:


1. Open the *Relationships* tab in the utility panel.


1. Click the *Relationships*  tab .

You can also point to the tab icon to view the name of the tab.

2. Right-click the trace that you want to mark or unmark with the *suspect* flag, and then click **Suspect**.

The context menu appears after you right-click the trace. If the suspect flag is already set, a checkmark appears beside the **Suspect** menu option:



After you have marked a trace with the suspect flag, a red exclamation point  appears on the *relationship* indicator. Also, a checkmark appears beside the **Suspect** option on the context menu.

Deleting a trace

Warning: Deleted traces cannot be restored. Unless you are sure you want to delete the trace, consider marking the trace with the suspect flag instead of deleting the trace.

Deleting a trace removes the relationship between two artifacts. After a trace is deleted, the trace no longer appears on the *Relationships* tab in the utility panel.

Tip: If you suspect that a trace is inaccurate or invalid, you may wish to mark it with the suspect flag instead of deleting the trace. Read more about [Adding and removing the trace suspect flag](#).

To delete a trace, perform the following steps:

1. Open the *Relationships* tab in the utility panel.

1. Click the *Relationships*  tab .

You can also point to the tab icon to view the name of the tab.

2. Right-click the trace that you want to delete.

The context menu appears.

3. Click **Delete** and then choose the direction you want.


The confirmation dialog appears.

4. Confirm the deletion.

Warning: Deleted traces cannot be restored. Unless you are sure you want to delete the trace, consider marking the trace with the suspect flag instead of deleting the trace.

About the traceability explorer


In the *Traceability Explorer*, you can view the trace relationships between selected artifacts in a grid layout or matrix.



Note: Artifacts that are not covered are called orphaned and are displayed in red font.

To learn more on the topic of trace relationships, see [Traceability and relationships](#).

The matrix lays out the trace relationships like an interactive Excel spreadsheet. The header rows and header columns contain any selected projects, folders and artifacts with direct hyperlinks to the original artifacts. At the center of the matrix, you can view the trace relationships that exist between the intersecting artifacts. The *Traceability Explorer* allows you to perform visual analyses of your trace relationships. For example, you can use the trace matrix to identify if you need to add any traces to a set of artifacts.




The *Traceability Explorer* also allows you to do the following:

- After the matrix is generated, you can still change the scope and filter the relationships that are displayed. You can filter by relationship type, relationship direction, suspect flag and orphaned items (no specified relationships). After making changes, click the **Generate Matrix** button to re-generate the traceability matrix.
- You can click the **Refresh** button at any time to refresh the information in the traceability matrix. This can be useful if you modify artifacts and want the traceability matrix to reflect the changes.
- You can run cross-project coverage analysis. Simply click the drop-down below the search boxes on the *Matrix Scope Selection* dialog and select another project.

Exporting a traceability matrix to Microsoft Excel

Blueprint allows you to conveniently export your traceability matrix to Microsoft Excel. You can then print your traceability matrix.



For more information about the in-Blueprint traceability matrix layout, see [About the traceability explorer](#).

Hyperlinks and icons are not preserved in the exported Excel spreadsheet.

Exporting a traceability matrix to Excel

To export a traceability matrix to Excel:


Important: If you have made any layout changes to your trace matrix, you should click **Generate Matrix** to finalize the changes before exporting your matrix (*Traceability Explorer* tab).

1. Click **Export** (*Traceability Explorer* tab).
The **Save As** dialog box appears.
2. Save your file as an **.xls** document in your desired location and then click **Save**.

You have successfully exported your traceability matrix to Excel. You can now open your file in Excel.

Exporting a traceability matrix to Microsoft Word

Blueprint allows you to conveniently export your traceability matrix to Microsoft Word. You can then print your traceability matrix.



For more information about the in-Blueprint traceability matrix layout, see [About the traceability explorer](#).

Hyperlinks and icons are not preserved in the exported Word document.

Exporting a traceability matrix to Word

To export a traceability matrix to Word:

Important: If you have made any layout changes to your trace matrix, you should click **Generate Matrix** to finalize the changes before exporting your matrix (*Traceability Explorer* tab).

1. Click **Export** (*Traceability Explorer* tab).

The *Save As* dialog box appears.

2. Save your file as an *.doc* document in your desired location and then click **Save**.

You have successfully exported your traceability matrix to Word. You can now open your file in Word.

Viewing trace relationships in a matrix


The *Traceability Explorer* allows you to perform visual analyses of your trace relationships. For example, you can use the trace matrix to identify if you need to add any traces to a set of artifacts.

To view the trace relationships between your artifacts in a matrix:

1. Select the artifacts that you want to include in your matrix.
2. Click **Open Traceability Explorer** (*Home* tab, *Relationships* group).



The *Matrix Scope Selection* dialog box appears.



3. If desired, you can remove artifacts or add more artifacts to the matrix scope.
Click **OK**.

The *Traceability matrix confirmation* dialog box may appear, informing you that the matrix may take some time to generate.

To prevent the message from appearing when generating matrices in the future: select **Do not show this message again**.

Click **Yes** to continue.

The Traceability Explorer appears in the main content area.

Note: Artifacts that are not covered are called orphaned and are displayed in red font.


The *Traceability Explorer* tab appears on the ribbon with various commands for re-defining scope, filtering the matrix, regenerating the matrix and exporting the matrix to other programs.

Collections

Blueprint gives you the ability to group requirements artifacts together into collections. Collections effectively let you remember what artifacts you have multi-selected within a single project. You can create as many collections as you like and apply a variety of actions to your collections, such as creating a review from a collection of artifacts.

Note: When you edit an artifact in your collection, you are editing the original artifact and not a copy. Collections do not contain artifact copies but rather are another way of efficiently accessing the original artifacts you selected for your collection.

Each project automatically has a *Collections* area, as you can see in the *explorer panel* below:



Baselines and reviews


A *baseline* artifact is a snapshot in time of one or more artifacts in a project. Baselines provide you with a reference point for viewing project artifacts as they existed at a particular point in time, even after the artifacts have changed. Baseline artifacts can be included in reviews to obtain feedback and approval.

A *review* artifact allows you to request artifact feedback and/or approval from stakeholders. Review artifacts can be set to one of two types: *informal review* (live artifacts), or *formal review* (baseline artifacts). You can only request approval or electronic signatures on artifacts if they are included in a formal review. If you create an informal review, review participants can add comments to artifacts, but the artifacts cannot be approved.

Note: A baseline must be *sealed* and *published* before you can include it in the review contents. This ensures that the artifacts do not change while the review is underway.

Finding your baseline and review artifacts

Baseline and review artifacts are special artifacts that are treated somewhat differently than other artifacts in Blueprint. Baseline and review artifacts are stored in a separate location in Blueprint. You can find your project's baseline and review artifacts by clicking the **Baselines and Reviews** folder located below your project in the *explorer* panel of Blueprint:



After you click the Baselines and Reviews folder for your project, your baseline and review artifacts are displayed in the main content area.

Reviewer and Approver Roles in Formal and Informal Reviews

A review artifact can be set to either a *formal review* or an *informal review*. Formal reviews contain *sealed baseline artifacts*, while informal reviews contain *live artifacts*.

- In a formal review (that is, *sealed baseline artifacts*), both reviewers and approvers have the ability to add comments to the artifacts. Approvers also have the ability to approve or disapprove artifacts. If the [electronic signature](#) option is enabled, approvers must verify their approvals/disapprovals via password or federated authentication. Reviewers cannot approve or disapprove artifacts.
- In an informal review (that is, *live artifacts*), both reviewers and approvers have the ability add comments to the artifacts. Reviewers cannot approve/disapprove artifacts in an informal review.

Baseline and Review Examples

Example

Lewis, a business analyst, is working on a set of requirements. He is close to completion and would like to obtain feedback from a few individuals.

In this scenario, Lewis would create an *Informal Review*, which is a review containing live artifacts. Lewis can continue to change the artifacts, and reviewers will always see the most recent published artifact when they open the artifacts from the review.

Example

Susan, a business analyst, is finished incorporating feedback from prior reviews that she has conducted. She is now confident that her artifacts are ready for approval.

In this scenario, Susan creates a baseline artifact. Next, she creates a review artifact and sets the type to **Formal Review**. Susan can then select the stakeholders that she wants to approve the requirements.

Example

Bill, a business analyst, is seeking approval on a complex use case artifact. In order to understand the use case, there are a number of textual requirements that must first be understood.

In this scenario, Bill starts by creating a baseline artifact. He then creates a **Formal** review, and includes the use case and the textual requirements in the review content. Bill only places a checkmark beside the use case artifact, because this is the only artifact that he needs approved. Read more about [selecting the artifacts that require approval](#).

The review participants now have the ability to review the textual requirements, and then approve or disapprove of the use case.

Example

Laura, a user experience designer, has completed her first draft of UI mockups. She would like to obtain feedback from numerous individuals, but is only seeking approval from a select few.

In this scenario, Laura creates a baseline artifact. She then creates a **Formal** review and adds the UI mockup artifacts to the review contents. Laura selects all individuals from the list, and then changes the **Permissions** for each individual to either *Reviewer* or *Approver*.

About Reviews


A *review* artifact allows you to request artifact feedback and/or approval from stakeholders. Review artifacts can be set to one of two types: *informal review* (live artifacts), or *formal review* (baseline artifacts). You can only request approval or electronic signatures on artifacts if they are included in a formal review. If you create an informal review, review participants can add comments to artifacts, but the artifacts cannot be approved.

Note: A baseline must be *sealed* and *published* before you can include it in the review contents. This ensures that the artifacts do not change while the review is underway.

When the review is active, you can [view the review status information](#) to determine which individuals have started reviewing the artifacts and whether or not any of the artifacts have been approved.

Finding your review artifacts

Review artifacts are special artifacts that are treated somewhat differently than other artifacts in Blueprint. Review artifacts are stored in a separate location in Blueprint. You can find your project's baseline and review artifacts by clicking the **Baselines and Reviews** folder located below your project in the *explorer* panel of Blueprint:



After you click the **Baselines and Reviews** folder for your project, your baseline and review artifacts are displayed in the main content area.

Key Concepts

REVIEWER AND APPROVER ROLES IN FORMAL AND INFORMAL REVIEWS

A review artifact can be set to either a *formal review* or an *informal review*. Formal reviews contain *sealed baseline artifacts*, while informal reviews contain *live artifacts*.

- In a formal review (that is, *sealed baseline artifacts*), both reviewers and approvers have the ability to add comments to the artifacts. Approvers also have the ability to approve or disapprove artifacts. If the [electronic signature](#) option is enabled, approvers must verify their approvals/disapprovals via password or federated authentication. Reviewers cannot approve or disapprove artifacts.
- In an informal review (that is, *live artifacts*), both reviewers and approvers have the ability add comments to the artifacts. Reviewers cannot approve/disapprove artifacts in an informal review.

REVIEW STATUS

The review can have one of the following statuses:

- *Draft*: The review has not yet been distributed to reviewers and approvers.
- *Active*: Reviewers and approvers have been notified about the review. Reviewers and approvers can view and comment on the review contents. Approvers can also approve or disapprove of review contents.
- *Closed*: Reviewers and approvers can no longer comment on the review contents after the review is *closed*. Approvers can no longer approve or disapprove the review contents.

MODIFYING AN ACTIVE REVIEW

When any review is *active*, you can still modify the list of review participants. Your ability to change other review parameters differs depending on whether you are modifying an *Informal Review* (live artifacts) or a *Formal Review* (baseline artifacts). The differences are:

- When an *informal* review is *active*, you can modify the review participants and change the review contents, but you cannot change the review to include *baseline* contents.
- When a *formal* review is *active*, you can modify the review participants and their approval permissions. You can also modify which artifacts are candidates for approval. You cannot, however, change the review content to include a different baseline.

Typical Usage of Reviews

Review artifacts can be beneficial at any phase in the project when you want to elicit feedback from others. Here's an example:

Example

Lewis, a business analyst, is working on a set of requirements. He is close to completion and would like to obtain feedback from a few individuals.

In this scenario, Lewis would create an *Informal Review*, which is a review containing live artifacts. Lewis can continue to change the artifacts, and reviewers will always see the most recent published artifact when they open the artifacts from the review.

Review artifacts are also useful when requirements are complete and final approval is required. Here's an example:

Example

Susan, a business analyst, is finished incorporating feedback from prior reviews that she has conducted. She is now confident that her artifacts are ready for approval.

In this scenario, Susan creates a baseline artifact. Next, she creates a review artifact and sets the type to **Formal Review**. Susan can then select the stakeholders that she wants to approve the requirements.

Review Artifact Properties

By default, a review artifact contains the following system properties:

- **Name:** Indicates the name of the **review**.
- **Id:** Provides a unique identifier for the **review**. The Id cannot be modified.
- **Type:** Indicates the type of artifact.
- **EndDate:** Indicates the review deadline date.
- **ReviewType:** Indicates whether the review is formal or informal.
- **ReviewURL:** Indicates the URL to access the review.
- **Status:** Indicates the status of the review.

The review can have one of the following statuses:

- **Draft:** The review has not yet been distributed to reviewers and approvers.
- **Active:** Reviewers and approvers have been notified about the review. Reviewers and approvers can view and comment on the review contents. Approvers can also approve or disapprove of review contents.
- **Closed:** Reviewers and approvers can no longer comment on the review contents after the review is *closed*. Approvers can no longer approve or disapprove the review contents.
- **Description:** Provides a description of the **review**.

Your instance administrator can configure standard properties for each standard artifact type.


Adding a review



This topic shows you how to add a review within the *Baselines and Reviews* folder.

Alternately, you can add a review using the **Add to Review** button without leaving your open artifact or artifact list. For more information about adding a review with the **Add to Review** button, see [Adding artifacts to an existing review](#)

To add a new review artifact:

1. Click the **Baselines and Reviews** folder in the explorer panel.



2. Click the **New** button  on the ribbon (*Home* tab, *Artifacts* group).
3. Select **Child Artifact**.
4. Click the review  icon.

Configuring a review


To configure a review, perform the following steps:

1. Provide a name for the review artifact.

Type a name into the **Name** field.

Tip: We recommend that you choose a name that is descriptive, but relatively short in length.

2. Set the review end date.

1. Click the *calendar*  button and select the date. Or, type the date into the field in the following format: *MM/DD/YYYY* (example: 11/14/2011).


Note: The review does not automatically close when the **End Date** is reached. The end date is a simple request for review participants to complete the review by a particular date.

3. Set the review contents.

1. Click the **Select Contents and Approval** Button. The *Choose review contents* dialog appears.
2. Select **Formal Review** or **Informal Review**. Formal reviews allow your collaborators to view, comment, and approve/disapprove artifacts in a sealed and published baseline. Informal reviews allow your collaborators to view and comment on live artifacts in the review.

Note: You must select your desired option prior to selecting the review contents. If you change this option after review contents have been selected, you will receive a warning and you must discard the selected review contents prior to continuing.


3. Search or browse to select the artifacts that you want to include in the review, and then move them to the right side of the dialog under *Review Contents*.



Tip: To select all child artifacts in a folder, select the folder and then click **Add Children**.

Note: If the **Do not count folders in the total number of artifacts to review** check box is selected, folders are not counted as artifacts in the review. The total number of viewed artifacts is displayed in *View Overview* and the *Reviewers Experience*.

- If you have selected a **Formal Review**, place a checkmark beside all the artifacts that you are seeking approval.




Tip: To select all artifacts in a folder, select the folder and then click **Select All**.

Note: Artifacts that appear on the right side of the dialog without a checkmark can be reviewed, but not approved.

5. Click **OK** to save the review contents.
4. Set the reviewers:
 1. Click the **Select Review Participants** button.
 2. Place a checkmark beside the appropriate individuals.
 3. Click **OK** to save the review participants.
5. Provide a description for the review.
 1. Type a description into the *Description* field.

The description can be used for any purpose, but it is typically used to provide information about the purpose of the artifact.
6. Start the review.

Choose one of the following options for starting the review:

 - Click the **Start Review** button in the *main content area* when the review artifact is open.
 - Click the **Start**  button located on the ribbon (*Baselines and Reviews* tab, *Review* group).

Note: The **Start Review** button cannot be selected until there is at least one artifact added to the review contents.

After you start the review, the *Status* changes to *Active*, and review participants are sent an email notification about the pending review request.

Note: Review artifacts are automatically published after you change the status of the review.


Modifying an Active Review

When any review is *active*, you can still modify the list of review participants. Your ability to change other review parameters differs depending on whether you are modifying an *Informal Review* (live artifacts) or a *Formal Review* (baseline artifacts). The differences are:

- When an *informal* review is *active*, you can modify the review participants and change the review contents, but you cannot change the review to include *baseline* contents.
- When a *formal* review is *active*, you can modify the review participants and their approval permissions. You can also modify which artifacts are candidates for approval. You cannot, however, change the review content to include a different baseline.

Adding artifacts to an existing review

Blueprint allows you to conveniently add one or more artifacts to an existing *informal* review without leaving your artifact list.



You can also create any type of review and add artifacts to it within the *Baselines and Reviews* folder (*Explorer Panel*). For more information about creating a review, see [Adding a review](#) and [Configuring a review](#).


To add an artifact to an informal review:

1. Select the artifacts in your artifact list that you want to add to an informal review.

Important: Individually select each artifact you want to include in the informal review. Selecting a folder does not automatically select all of its child artifacts for inclusion in the review.

You can also add a single artifact to a review when the artifact editor is open.

2. Click the *Add To* button on the ribbon and then click **Review** (*Home* tab, *Artifacts* group).



The *Add to Review* dialog box appears.

3. Select your review(s) and then click **OK**.

The *Confirmation* dialog box appears.

Click **OK**.

Your artifact(s) have been added to your selected review(s).

Next, you will probably want to configure the review. For more information about configuring the review, see [Configuring a review](#).

Viewing review status information

After you have started a review, the *Review Status* is set to *Active*. At this point, you may wish to view status information so you can determine which review participants have started viewing the review contents, and whether or not the artifacts have been approved, disapproved, or not yet specified. In addition to viewing status information for *active* reviews, you can also view review status information for *Closed* reviews.

To view the review status information:

1. Open the review artifact.
2. Click the **View Overview / View Details** toggle link to view the review status in either the *detailed* or *overview* layout. The two different layouts are explained below.


OVERVIEW LAYOUT

Note: If you selected the **Do not count folders in the total number of artifacts to review** check box during the creation of the review, folders are not counted as artifacts in the review. As a result, folders are not counted in the total number of viewed artifacts.

The *Overview* layout provides a graphical representation of the review status.


The *Contents* chart provides:

- number of viewed artifacts:
 - the number of artifacts that have been viewed by all review participants
 - the number of artifacts that have been viewed no review participants, or only some review participants
- number of artifacts by approval status:
 - number of artifacts that have been *Approved* by all review participants
 - number of artifacts that have been *Disapproved* by all review participants
 - number of artifacts that have at least one *Pending Approval* status



The *Review Participants* chart provides:

- the total number of review participants in each stage of the review (*Complete*, *In Progress* and *Not Started*).
- the total number of *Approved*, *Disapproved* and *Pending Approval* artifacts by review participant



DETAILS LAYOUT

The *Details* layout provides detailed numerical status information about the review.

Contents Table

The *Contents* table provides a breakdown, by artifact, of the total number of *Approved*, *Disapproved*, and *Not Specified* statuses. The Approval column is set to Not Requested if approval was not requested for that particular artifact.

Contents

Name	ID	Approval	
▶ Executive Sponsor Interview	PF185117	Approval Not Requested	
▶ Online Banking Website	PF185118	Approval Not Requested	
▶ Apply for Credit Card Online	PF185123	Approval Not Requested	
Acronyms	GL185124	✓1✗0○3	
Business Terms	GL185125	✓0✗0○4	
Technical Terms	GL185128	✓0✗0○4	
▶ Actors	PF185129	Approval Not Requested	
Online Banking System Interfaces	GD185130	✓0✗0○4	
▶ Document - Online Banking Copy	DOC195805	✓0✗0○4	
▶ Credit Card Management Process	BP185136	✓0✗0○4	

[Select Contents and Approval](#) [View Details](#)

To view the approval status for an individual artifact, select the artifact in the contents table, and click the **View Details** link located below the table. The contents *View Details* dialog looks like this:

View Details ✕

Artifact Name: Acronyms

Reviewer	View State	Approval
Allison Burnett	Not Viewed	Approval Not Requested
Steph Hubert	Viewed	✓ Approved
Matt Dodgson	Not Viewed	Approval Not Requested
Christina McNish	Not Viewed	○ Pending Approval

[Close](#)

Reviewer Participants Table

The *Review Participants* table provides the following information about the participants in your review:

- **Permissions:** Provides the review permissions of each individual. All review participants have permissions to review artifacts. If a user has *Approver* permissions, the user can approve or disapprove artifacts. *Approver* permissions can only be assigned in a formal review. The permissions can be set to *Reviewer* or *Approver*.

- **Status:** Provides the review status of the individual. The status can be set to *Not Started*, *In Progress*, or *Completed*.
- **Approval:** Provides the approval status for each individual. The *Approval* column provides the total number of *Approved*, *Disapproved*, and *Pending Approval* artifacts for each individual.



Review Participants

Review Participants	Permissions	Status	Approval	
Allison Burnett	Reviewer ▾	Not Started	Approval Not Requested	
Steph Hubert	Approver ▾	In Progress	✓3✗2🕒44	
Matt Dodgson	Reviewer ▾	Not Started	Approval Not Requested	
Christina McNish	Approver ▾	Completed	✓3✗0🕒46	

Total: 1 Review Participants are Complete, 1 Review Participants are In Progress, 2 Review Participants have Not Started

[Select Review Participants](#) [View Detail](#)

To view the approval progress of an individual, select the individual in the review participants table, and click the **View Details** link located below the table. The review participants *View Details* dialog looks like this:

View Details

Reviewer's Name: Steph Hubert

ID	Name	View State	Approval
PF185117	Executive Sponsor Interview	Not Viewed	Approval I
PF185118	Online Banking Website	Not Viewed	Approval I
PF185123	Apply for Credit Card Online	Viewed	Approval I
GL185124	Acronyms	Viewed	✓ Approv
GL185125	Business Terms	Not Viewed	🕒 Pending
GL185128	Technical Terms	Viewed	🕒 Pending
PF185129	Actors	Not Viewed	Approval I
GD185130	Online Banking System Interfaces	Not Viewed	🕒 Pending
DOC195805	Document - Online Banking Copy	Not Viewed	🕒 Pending
BP185136	Credit Card Management Process	Not Viewed	🕒 Pending
PF185137	Generated Word Document	Not Viewed	Approval I

Close

Closing a review


The purpose of closing a review is to prevent review participants from adding additional comments to artifacts in the review. It also prevents review participants from changing the approval status of artifacts.

Note: After a review is *closed*, it cannot be changed back to an *active* status.

To close a review:

1. Open the review artifact that you want to close.
2. Click **Close Review**.

Choose one of the following options for closing the review:

- Click the **Close Review** button in the *main content area* when the review artifact is open.
- Click the **Close**  button located on the ribbon (*Baselines and Reviews* tab, *Review* group).

Note: Review artifacts are automatically published after you change the status of the review.

Reviewers and approvers can no longer comment on the review contents after the review is *closed*. Approvers can no longer approve or disapprove the review contents.

Creating a follow up review

Using a *follow up review*, you can quickly create a new review artifact based on an existing closed review with the same review contents and the same review participants. The review participants's *view state*, approvals and disapprovals are carried over into the new review. Review participants can see what, if any, artifacts changed in the *Reviewers Experience*. The author of the review can modify the contents and review participants, if desired. Follow up reviews are beneficial for many reasons. For instance, after you have incorporated stakeholder feedback from a previous review, you may wish to send the same review contents for an additional review, to the same list of stakeholders.

Note: You can only create follow up reviews for reviews that are *closed*.

To create a follow up review:

1. Open the review artifact that you want to follow up on.
2. Click **Follow Up**.



The **Follow Up** button is located on the ribbon (*Baselines and Reviews* tab, *Review* group).

After you click **Follow Up**, the *Confirmation* dialog appears.

3. Click **Yes** to confirm that you want to create a follow up review.

A new review artifact is created with the same review contents and review participants. The name of the new review artifact is the same, but **follow-up** is appended to the end of the name.

4. Configure and start the follow up review. Read more about [configuring a review](#).

Deleting a review

Note: Review artifacts cannot be deleted if the *Review Status* is *Active* or *Closed*. You can only delete *Draft* review artifacts.

Tip: Consider creating folders to organize your review artifacts. For example, you may want to create a folder named **Archive** to store the artifacts that you used for testing, or those that you no longer need.

To delete a review:

1. Open the **review** that you want to delete, or select the **review** in the artifact list.
 - To open an artifact, click the artifact ID link that is displayed in the ID column of the artifact list. Or, right-click the artifact in the artifact list and then click **Open**.
 - To select an artifact, click a row in the artifact list.

2. Click **Delete**.

You can find the **Delete** button in the following locations:

- on the ribbon (*Home* tab, *Artifacts* group).
- on the context menu when you right-click an artifact in the artifact list.

After you click delete, the *Confirmation* dialog appears.

3. Confirm the deletion.

Click **Yes** to confirm deletion, or click **No** to cancel.

About the utility panel reviews tab

The *reviews* tab provides you with a list of all reviews that contain the artifact. From this tab, you can view summary information about the reviews, or open the review for additional details.

The *reviews* tab in the utility panel looks like this:

Reviews	Status	Approval	Created Date
Live Artifact Review	Active	N/A	05/04/2013
Formal Review	Active	✓1 ✗0 ⌚2	09/04/2013

▼

RVP4995933: Live Artifact Review

▲ Details

Contents	Live Artifacts
Artifact Version	Current

▲ Review Participants View State (3 Review Participants)

Review Participants	Viewed
Docs Tester 2	NotViewed
Christina McNish	NotViewed
Docs tester	NotViewed

A label is displayed at the top of every tab in the utility panel. It provides the ID and name of the artifact or sub-artifact you are viewing. For example:

» Utility Panel

GD4668410: Online Banking System Interfaces

▲ Properties

Name	Online Banking System...
Id	GD4668410
Type	Generic Diagram
Width	1308
Height	768

UNDERSTANDING THE REVIEW SUMMARY TABLE

The top portion of the *reviews* tab displays a table of information with the following columns:

- *Review Packages*: Provides the name of the review.

Tip: You can click the review link to open the review in the *main content area*.

- *Status*: Indicates the status of the review. Read more about [review status](#).
- *Approval*: Indicates the total number of artifacts that are approved, disapproved, or not yet specified. This column displays **N/A** if approvals were not requested (example: informal reviews).

- *Created Date*: Indicates the creation date of the review. This date provides the date the review artifact was created, which is not always the same date the artifact became *active*.

UNDERSTANDING THE REVIEW DETAILS

The review details are displayed at the bottom of the *reviews* tab in the utility panel as soon as a review is selected.

The review summary details panel is labeled with the review ID and name. Example

RVP4995933: Live Artifact Review

To view additional details about the changes, simply expand and collapse the headings (example: *Details*, *Review Participants View State*) to view more details about the review.

About the Reviewers Experience

The *Reviewers Experience* refers to the user interface used by review participants. This is a very simple yet powerful interface designed specifically for supporting review participant tasks.

Artifacts included in a review can have one of the following status values:

- *Not Specified*: You have not yet approved or disapproved the artifact.
- *Approved*: You have approved the artifact.
- *Disapproved*: You have disapproved the artifact.
- Custom status

Note: Each custom status must have a type of either *Approved* or *Disapproved* (example: *Approved with Comments*)

A Typical Review Process

A typical review process happens as follows. The review participant will:

1. Open the review.
2. View the contents of each artifact.
3. Provide feedback by adding new comments and replying to existing comments.
4. Approve or disapprove each artifact.
5. Change your review status to *completed*.

Note: All artifacts in a review are read-only in the Reviewers Experience. Live artifacts may be changed during the review (but not using the Reviewers Experience) while baseline artifacts cannot be changed. However, you can use the **New Comment** button on the ribbon (*Home* tab, *Artifact* group) to add a comment to any artifact in the review package. When you click the **New Comment** button, the *Discussions* tab is automatically opened in the utility panel.

About the reviewers experience layout

The *Reviewers Experience* refers to the user interface used by review participants. This is a very simple yet powerful interface designed specifically for supporting review participant tasks. The *Reviewers Experience* layout is similar to the general Blueprint layout, with a few exceptions:

- there is no explorer panel
- the ribbon tabs, groups and buttons differ

The *Reviewers Experience* looks like this:


The screenshot displays the 'Reviewers Experience' interface. On the left, a table lists artifacts for review, including 'Wyngs Air Domain Diagram', 'System Overview', 'Traveler Booking', 'Comparison Shop', 'Register for Reward Program', and 'Organization Chart'. The table columns are Approval, Contents, ID, Description, Indicators, and View State. On the right, an organization chart for 'Wynys Air - Reservation System' is shown, with Arno Hartevelde (President) at the top, branching into Phil Spencer (Sales SVP) and Phyllis Harris (Manufacturing VP), who further branch into various roles like John Kane, Denise Smith, Jim Daly, and Jill Frank.

When you first open the *Reviewers Experience*, a list of artifacts requiring your review or approval appears on the leftmost side of the window. The progress indicator at the bottom of the left panel tracks your status as you proceed with the review. For more information about the review, see [Review details](#).

Note: By default the list that appears consists only of artifacts requiring review or approval. However, you can also view baseline content that was excluded (formal reviews) or parent relationships that were excluded (informal reviews). To view all content, click the **Show All Review Content** button (*View* tab, *Artifact List* group).

FEATURES AND MENU FUNCTIONS

The *Home* tab on the ribbon provides you with some useful features to enhance your review experience:




- **Refresh:** Refreshes the artifact that you are currently viewing.
- **Go To:** Allows you to quickly navigate to an artifact by its ID.
- **Follow:** Allows you to follow or unfollow an artifact.
 - **Follow:** Allows you to begin following an artifact.
 - **Unfollow:** Allows you to unfollow an artifact that you are currently following.
- **Approved:** Sets the review status of the artifact to *Approved*. You can only approve artifacts if you have *approver* permissions and if you are reviewing a sealed baseline artifact. Approver permissions are set by the author of the review artifact.
- **Pending Approval:** Sets the review status of the artifact to *Pending Approval*, which indicates that you have not yet approved or disapproved the artifact. This button is only available if you have *approver* permissions and if you are reviewing a sealed baseline artifact.

- **Disapproved:** Sets the review status of the artifact to *Disapproved*. You can only disapprove artifacts if you have *approver* permissions and if you are reviewing a sealed baseline artifact. Approver permissions are set by the author of the review artifact.
- **New Comment:** Opens the *Discussions* tab in the utility panel, allowing you to add a new comment to the artifact.
- **Mark Review Complete:** Toggles your review status between *Completed* and *In Progress*.

REVIEW DETAILS

When you open a review in the *Reviewers Experience*, the following information is available in the first tab:



- **Properties:**
 - **Name:** Indicates the name of the review artifact.
 - **Status:** Indicates the status of the review.

The review can have one of the following statuses:

- **Draft:** The review has not yet been distributed to reviewers and approvers.
- **Active:** Reviewers and approvers have been notified about the review. Reviewers and approvers can view and comment on the review contents. Approvers can also approve or disapprove of review contents.
- **Closed:** Reviewers and approvers can no longer comment on the review contents after the review is *closed*. Approvers can no longer approve or disapprove the review contents.

Note: *Draft* reviews cannot be opened in the *Reviewers Experience*.

- **ID:** Indicates the ID of the review.
- **Permissions:** Indicates the reviewer participant permission level:
 - *Approver:* Indicates that you are an approver, and therefore you can approve or disapprove the artifacts. You can also add comments to the review contents.
 - *Reviewer:* Indicates that you are a reviewer, and therefore you can add comments to the review contents, but you cannot approve or disapprove artifacts in the review.
- **End Date:** Indicates the end date of the review.

Note: The review does not automatically close when the **End Date** is reached. The end date is a simple request for review participants to complete the review by a particular date.

- **Your Status:**
 - **Your Status:** Provides the review coordinator with information about the progress of each stakeholder. **Your Status** can be set to one of the following:
 - *Not Started:* Indicates that you have not yet started reviewing the contents.
 - *In Progress:* Indicates that your review is in progress. The status is automatically set to *In Progress* as soon as you open the review contents.
 - *Completed:* Indicates that you have set your review status to *Completed*. You must perform this action manually.
 - **Complete the Review / Re-enter the Review** toggle button: Toggles **Your Status** between *In Progress* and *Completed*. The **Complete** button on the ribbon (*Home* tab, *Review* group) does the same thing.
 - **View All Artifacts** button: Opens an artifact list with all the artifacts listed. After you click **View All Artifacts**, the **Your Status** field is automatically changed from *Not Started* to *In Progress*.

Adding comments to an artifact in a review

Adding comments to review artifacts is the most common action that you will perform while participating in a review. Adding comments allows you to provide feedback and suggestions about the artifacts contained in the review.

Note: All artifacts in a review are read-only in the Reviewers Experience. Live artifacts may be changed during the review (but not using the Reviewers Experience) while baseline artifacts cannot be changed. However, you can use the **New Comment** button on the ribbon (*Home* tab, *Artifact* group) to add a comment to any artifact in the review package. When you click the **New Comment** button, the *Discussions* tab is automatically opened in the utility panel.


To add comments to an artifact in a review:

1. Open the review.

Choose one of the following options to open the review:

- Click the link in the review notification email.
- Click the review link located on the right side of your activity center.

- Click the **Open Review** button located in the *main content area* of the review artifact, if you have access to open the artifact.
2. View the artifacts included in the review.
 1. Click the **View All Artifacts** button to view the artifacts in the review.
3. Open an artifact.

Click the artifact ID link of the artifact you want to open.
4. Open the *Discussions* tab in the utility panel.
 1. Click the *Discussions* tab  in the utility panel.
5. Add a new comment or reply to an existing comment.

Read more about [Adding a new comment](#) and [Replying to an existing comment](#).

Changing the approval status of an artifact



If a review is *active*, you can change the approval status of artifacts. However, you can only change the approval status of artifacts if your review status is set to *InProgress*. If your review status is set to *Completed*, you must first change it to *InProgress*. Read more about [Changing your review status](#).


To change the approval status of an artifact:

1. Open the review.

Choose one of the following options to open the review:

 - Click the link in the review notification email.
 - Click the review link located on the right side of your activity center.
 - Click the **Open Review** button located in the *main content area* of the review artifact, if you have access to open the artifact.
2. View the artifacts included in the review.
 1. Click the **View All Artifacts** button to view the artifacts in the review.
3. Open an artifact.

Click the artifact ID link of the artifact you want to open.
4. Approve or disapprove the artifact.
 1. Click the **Approved**  or **Disapproved**  button on the ribbon (*Home* tab, *Artifact* group).

Note: You can also remove the approval status by clicking the **Pending Approval**  button on the ribbon (*Home* tab, *Artifact* group).

The *Electronically Sign Artifact* dialog box appears if electronic signature validation is required.

To provide your electronic signature, verify your identity by providing your login credentials.

Changing your review status

It is best practice to change your review status to *completed* after you have finished reviewing the artifacts in a review. This helps other users to determine how many people have completed the review. However, you may wish to re-enter the review if you have additional comments to add, or if you wish to change the approval status of artifacts in the review.

As long as the review is still *active*, you can change your review status.

To change your review status:


1. Open the review.

Choose one of the following options to open the review:

- Click the link in the review notification email.
- Click the review link located on the right side of your activity center.
- Click the **Open Review** button located in the *main content area* of the review artifact, if you have access to open the artifact.

2. Toggle your status between *Completed* and *In Progress*.

Choose one of the following methods to toggle your status:

- Click the *mark review complete*  button on the ribbon (*Home* Tab, *Review* group) to toggle your review status.
- Click the **Re-enter the Review/Complete the Review** toggle button in the *main content area* of the review.

As you toggle your status, the *Your Status* field in the *main content area* switches between *Completed* and *In Progress*.

About electronic signatures

Note: Electronic signatures can only be requested for formal reviews.

Blueprint allows review coordinators to request electronic signatures from approvers. An *electronic signature* is an indication that a requested approver verified his or her identity via a means of authentication and provided input on the review. E-signature is a mode of verification that can help you meet certain industry standards and auditing requirements.

Electronic signatures and approvers

The electronic signature feature can be enabled within a new formal review.

Properties

Name: Release 2.0 Review

End Date: EnterDate Review Type: Formal

Status: Draft Start Review

Review URL: Launch Reviewers Experience

☒ Require electronic signatures for formal reviews

☐ Mark Review As Complete only when all artifacts have been reviewed

Note: Project administrators can set all new formal reviews to require electronic signatures by default in **Project Settings** (*Project Administration Console*).

When this option is enabled, electronic signatures are enabled for all approvers in the formal review.

After a review has started, review participants can launch the review in the *Reviewers Experience*. When the review participant chooses to approve or disapprove an artifact, Blueprint prompts the user for an electronic signature. The user must confirm his or her identity using federated authentication or password authentication.

Electronically Sign Artifact

Electronically sign with Corporate Credentials Go

OR

Enter your password to electronically sign:

I Agree I Decline

Note: The federated authentication section of the *Electronically Sign Artifact* dialog can be customized within the *Instance Administration Console*.

The electronic signature and approval status details appear on the *Reviews* tab (bottom pane) when the artifact is selected.

The electronic signature and approval status details are organized into the following columns:

- Review Participants
- Approval
- Electronically Signed On

» Utility Panel

DOC1978571: AirportsList.xls

Reviews	Status	Approval	Created Date
First Review	Closed	✓1✗0○1	01/11/2013
Second Review	Active	N/A	04/11/2013
Third Review	Active	✓1✗0○0	05/11/2013

RVP2124968: First Review

Details

Contents	2124967: New Baseline 1
Artifact Version	1

Review Participants Approval (2 Review Participants)

Review Participants	Approval	Electronically Signed On
Christina	Approved	01/11/2013 11:23:37 AM
Jamal	Pending Approval	

Requesting electronic signatures for a formal review

Note: Project administrators can set all new formal reviews to require electronic signatures by default in **Project Settings** (*Project Administration Console*).

Blueprint allows review creators to request electronic signatures from approvers in a formal review. Electronic signatures can only be enabled for all approvers in a formal review.

To request electronic signatures from approver(s):

Note: In order to configure a formal review package, you must first create a baseline to include in the review package.

1. Create a review package.
Click the **New** button, point to *Child Artifact* and then click **Review**.
2. Select a baseline to include in the review.
Click **Select Contents and Approval**.
The *Choose Review Contents* dialog box appears.
Select **Formal Review**.
Select your baseline and then click **Add**.
Click **OK**.

Note: Only after you select your baseline can you enable **Require electronic signatures for formal reviews**.

3. Select **Require electronic signatures for formal reviews**.
The electronic signature feature can only be enabled for all approvers in a formal review.

Baselines and Reviews : BP Airways >
RVP7: * Release 2.0 Review

Properties

Name: Release 2.0 Review

End Date: EnterDate Review Type: Formal

Status: Draft Start Review

Review URL: Launch Reviewers Experience

☒ Require electronic signatures for formal reviews

☐ Mark Review As Complete only when all artifacts have been reviewed

4. Add the approvers.

Click **Select Review Participants**.

Select the users you want to include in your review and then click **OK**.

5. Start the review.

Click the **Start Review** button.

To make the review live, click the **Publish** button (*Artifacts* group, *Home* tab).

When approvers begin the review and either approve or disapprove an artifact, they must provide electronic signatures either via federated authentication or password authentication.

Generating an office document

Blueprint allows you to generate Microsoft Word and Microsoft Excel documents using the data from your Blueprint artifacts.

Before you can generate office documents, your instance administrator or project administrator must author a template and add the template to the [instance](#) or [project](#).

Here's an example of a generated document in MS Word format:

Detailed Specification

Project **Created By** John Smith

Created 15/03/2012 11:23:45 AM

Document Source Live Artifacts

Requirements

BR555211: Business Requirement[Business Requirement]

Version: 1

Published by: John Smith

Name	Value
ID	BR555211
Name	Business Requirement
Description	
Outline	1.1.
Custom Properties	
Owner	
Priority	

BR555215: Business Vision[Business Requirement]

Version: 1

Published by: John Smith

Name	Value
ID	BR555215
Name	Business Vision
Description	
Outline	3.1.1.1.
Custom Properties	
Owner	
Priority	

Here's an example of a generated document in MS Excel format:

	A	B	C	D	E	F	G	H	I	J	K
1	NN	Blueprint Hierarchy	Outline Number	ID	Name	Blueprint Type	Description	Owner	Priority		
2	1	+		1.1.	BR555 211	Business Requirement	Business Requirement				
3	2	+		3.1.1.1.	BR555 215	Business Vision	Business Requirement				
4	3	+		3.1.2.1.	BR555 216	Business Requirement	Business Requirement				
5	4	+		3.1.2.2.	UR555 217	User Requirement	User Requirement				
6	5	+		3.1.3.1.	FR555 218	Functional Requirement	Functional Requirement				
7	6	+		3.1.3.2.	NR555 219	Non- Functional Requirement	Non- Functional Requirement				
8	7	+		3.2.1.1.	BR555 220	Business Vision	Business Requirement				
9	8	+		3.2.2.1.	BR555 221	Business Requirement	Business Requirement				
10	9	+		3.2.2.2.	UR555 222	User Requirement	User Requirement				
11	10	+		3.2.3.1.	NR555 223	Non- Functional Requirement	Non- Functional Requirement				
12	11	+		3.2.3.2.	FR555 224	Functional Requirement	Functional Requirement				
13											
14											

You can export artifact data to a Microsoft Word or Microsoft Excel document, assuming your instance administrator or project administrator has added templates to the instance or project.

To generate a Microsoft Word or Microsoft Office document:

1. Click the **Office Document** button on the ribbon (*Import/Export* tab, *Export* group).
The *Source Project* screen of the *Generate Office Documents* dialog appears.
2. Select the project that contains the artifacts that you want to include in the generated office document, and then click **Next**.
The *Document Template* screen appears.
3. Select the document template to use, and then click **Next**.
The name and format of each template is displayed. The template format can be MS Word or MS Excel. MS Word templates can only produce MS Word output. MS Excel templates can only produce MS Excel output.

Note: If there are no templates listed, your instance administrator or project administrator must author a template and add the template to the instance or project.

After you click **Next**, The *Document Source* screen appears.

4. Select whether you want to use data from **live artifacts**, or data from a **baseline or review**, and then click **Next**.

If you select the baseline or review option, you must select a baseline or review.

After you click **Next**, the *Document Scope* screen appears.

5. Select the document scope, and then click **Next**.

Select the artifact(s) that you want to include in the document. Simply select the artifacts and click the **Add** button.

Tip: To select all artifacts in a folder, select the folder and then click **Select All**.

6. Specify your document output options.


- Specify the **Document Name** and location for the generated document.
- **Generate images for document output:** Defines whether or not you want to generate images for graphic artifacts that you are exporting, such as diagrams. If this option is disabled, images are not exported.

If this option is disabled, images (that is, graphic artifacts) are not included in the document output.

When office documents are generated in Blueprint, they are automatically saved in Blueprint for reference purposes.

7. Click **Finish**.

The document generation has been scheduled and placed into the job queue.

When the document has generated successfully, you can click the **notification** icon () to see the new document artifact. Simply open the document artifact and click the **Download** link to download or view the generated Office document.

Note: If you are using Internet Explorer 8, you must enable the *automatic prompting for file downloads* security setting before you can download the file from Blueprint. To enable this setting, click **Tools > Internet Options > Security > Custom level... > Downloads** and then enable the **Automatic prompting for file downloads** option.